



One Identity Manager 8.2

Authorization and Authentication Guide

Copyright 2021 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC.

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC.
Attn: LEGAL Dept
4 Polaris Way
Aliso Viejo, CA 92656

Refer to our Web site (<http://www.OneIdentity.com>) for regional and international office information.

Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <http://www.OneIdentity.com/legal/patents.aspx>.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.OneIdentity.com/legal. All other trademarks are the property of their respective owners.

Legend

 **WARNING:** A WARNING icon highlights a potential risk of bodily injury or property damage, for which industry-standard safety precautions are advised. This icon is often associated with electrical hazards related to hardware.

 **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.

One Identity Manager Authorization and Authentication Guide
Updated - 02 December 2021, 12:47
Version - 8.2

Contents

About this guide	7
One Identity Manager application roles	8
Application roles overview	9
Application roles for basic functions	10
Application role for the Operations Support Web Portal	12
Application role for Compliance & Security Officers	12
Application role for auditors	13
Application roles for identity audit	13
Application roles for company policies	15
Application roles for attestation	16
Application roles for subscribable reports	17
Application roles for management levels	18
Application roles for business roles	18
Application roles for organizations	19
Application for employee administrators	21
Application roles for the IT Shop	21
Application roles for target systems	23
Application roles for Universal Cloud Interface	24
Application role for Privileged Account Governance	25
Application roles for Application Governance	26
Application roles for custom tasks	26
Implementing the application roles	27
Creating and editing application roles	28
Main data of application roles	29
Assigning employees to application roles	30
Custom extension of application role permissions	31
Creating and editing dynamic roles for application roles	32
Specifying mutually exclusive application roles	33
Assigning subscribable reports to application roles	33
Assigning extended properties to application roles	34
Generating assignment resources for application roles	35

Reports about application roles	35
Granting One Identity Manager schema permissions through permissions groups	36
Predefined permissions groups and system users	37
Rules for determining the valid permissions for tables and columns	39
Editing permissions groups	42
Dependencies between permissions groups	43
Permissions group dependencies	44
Copying permissions groups	45
Creating permissions groups	46
Permissions group properties	47
Editing system users	47
Creating system users	48
System users' passwords	49
System user properties	49
Adding system users to permission groups	50
Which employees use the system user?	52
Dynamic system user	52
Permissions for tables and columns	53
Displaying permissions of a permissions group	53
Displaying permissions for tables	54
Editing table permissions	55
Editing column permissions	56
Copying table permissions and column permissions	57
Simulating permissions for system users	58
Displaying permissions for objects	60
Displaying permissions for the current user	61
Assigning role-based permissions groups to an applications	61
Managing permissions to program features	63
Displaying the current user's program functions	63
Assigning program functions to permissions groups	64
Permissions for running scripts	64
Permissions for running methods	65
Permissions for triggering processes	66
Modifying permissions for running actions in the Launchpad	67

One Identity Manager authentication modules	68
System users	69
Generic single sign-on (role-based)	69
Employee	71
Employee (role-based)	72
Employee (dynamic)	73
User account	74
User account (role-based)	74
Account based system user	75
Active Directory user account	76
Active Directory user account (role-based)	77
Active Directory user account (manual input)	78
Active Directory user account (manual input/role-based)	79
Active Directory user account (dynamic)	80
LDAP user account (role-based)	81
LDAP user account (dynamic)	83
HTTP header	85
HTTP header (role-based)	86
OAuth 2.0/OpenID Connect	87
OAuth 2.0/OpenID Connect (role-based)	88
Synchronization authentication module	89
Web agent authentication module	90
Component authentication module	90
Crawler	91
Password reset	91
Password reset (role-based)	93
Decentralized identity	94
Decentralized Identity (role-based)	95
Editing authentication modules	96
Enabling authentication modules	97
Assigning authentication modules to applications	97
Disabling or enabling authentication modules for applications	98
Authentication module properties	99
Initial data for authentication modules	99
Configuration data for system user dynamic authentication	104

Example of a simple system user assignment	105
Example of a system user assignment using a selection criterion	106
Example of a function group assignment	107
Checking authentication	108
OAuth 2.0 / OpenID Connect configuration	109
Expiry of the OAuth 2.0/OpenID Connect authentication	109
Creating the OAuth 2.0/OpenID Connect configuration	111
Assigning OAuth 2.0/OpenID Connect configuration to web applications	116
Displaying the configuration of the identity provider and the OAuth 2.0/OpenID Connect applications	117
Specifying enabled and disabled columns for logging in	118
Logging information about OAuth 2.0/OpenID Connect authentication	119
Multi-factor authentication in One Identity Manager	120
Editing table properties	122
Preparing the Starling 2FA token request	122
Requesting a security code	123
Multi-factor authentication with One Identity Defender	124
Configuring RSTS for multi-factor authentication	125
Configuring authentication with OAuth 2.0/OpenID Connect in the Web Portal	126
Configuring authentication with OAuth 2.0/OpenID Connect	127
Authenticating other applications using OAuth 2.0/OpenID Connect	128
Granular permissions for the SQL Server and database	130
Displaying database server logins	130
Displaying users' access levels	131
Displaying server roles and database roles permissions	131
Installing One Identity Redistributable STS	132
Appendix: Program functions for starting the One Identity Manager tools	133
Appendix: Minimum access levels of One Identity Manager tools	136
About us	139
Contacting us	139
Technical support resources	139
Index	140

About this guide

The *One Identity Manager Authorization and Authentication Guide* describes the basics and features of One Identity Manager's own roles and permissions model.

This guide is intended for end users, system administrators, consultants, analysts, and any other IT professionals using the product.

NOTE: This guide describes One Identity Manager functionality available to the default user. It is possible that not all the functions described here are available to you. This depends on your system configuration and permissions.

This shows you an overview of One Identity Manager's application roles, permissions groups, and system users. The guide explains how to set up and implement application roles. The guide also explains how you grant permissions for the tables and columns of the One Identity Manager schema. In addition, you will find an overview of the various One Identity Manager authentication modules.

Available documentation

You can access One Identity Manager documentation in the Manager and in the Designer by selecting the **Help > Search** menu item. The online version of One Identity Manager documentation is available in the Support portal under [Technical Documentation](#). You will find videos with additional information at www.YouTube.com/OneIdentity.

One Identity Manager application roles

You can use the One Identity Manager role model to control edit permissions for One Identity Manager users. This role model takes into account technical aspects, for example, One Identity Manager tool administrative permissions, as well as functional aspects, which result from One Identity Manager user tasks within the company structure (for example, permissions for approving requests). One Identity Manager makes so-called application roles available.

Application roles have the following aims:

- Program functions, employees, company resources, approval workflows and approval policies are assigned to fixed application roles. Permissions for these application roles must not be defined specifically for the company. This simplifies how you manage permissions.
- Enables audit secure internal administration of One Identity Manager users and their permissions. Permissions can be granted through assignment, request, and approval or by calculation on account of specific properties. The plausibility of the permissions can be tested at any time with the attestation function.
- Users are provided with initial permissions, which they required for carrying out their tasks. This is a way, for example, to create initially required user accounts.

Application roles can be linked to permissions groups whose edit permissions are predefined by One Identity Manager. Controlling permissions

- Access to objects and their properties
- Navigation configuration in administration tools
- Which interface forms and tasks are displayed
- Availability of special program functionality

Users must be role-based to use application roles for logging in to One Identity Manager. Role-based authentications module finds the valid edit permissions from all the user's application roles. This provides the One Identity Manager user with permissions corresponding to their application roles for the One Identity Manager functions when they log onto One Identity Manager tools.

Detailed information about this topic

- [Application roles overview](#) on page 9
- [Implementing the application roles](#) on page 27
- [Creating and editing application roles](#) on page 28

Related topics

- [Granting One Identity Manager schema permissions through permissions groups](#) on page 36
- [One Identity Manager authentication modules](#) on page 68

Application roles overview

One Identity Manager supplies default application roles whose permissions are matched to the different task and functions. Assign employees to default applications who take on individual tasks and functions. You can also create your own application roles for custom defined tasks.

NOTE: Default application roles are defined in One Identity Manager modules and are not available until the modules are installed. You cannot delete default application roles.

Detailed information about this topic

- [Application roles for basic functions](#) on page 10
- [Application role for the Operations Support Web Portal](#) on page 12
- [Application role for Compliance & Security Officers](#) on page 12
- [Application role for auditors](#) on page 13
- [Application roles for identity audit](#) on page 13
- [Application roles for company policies](#) on page 15
- [Application roles for attestation](#) on page 16
- [Application roles for subscribable reports](#) on page 17
- [Application roles for management levels](#) on page 18
- [Application roles for business roles](#) on page 18
- [Application roles for organizations](#) on page 19
- [Application for employee administrators](#) on page 21
- [Application roles for the IT Shop](#) on page 21
- [Application roles for target systems](#) on page 23
- [Application roles for Universal Cloud Interface](#) on page 24
- [Application role for Privileged Account Governance](#) on page 25

- [Application roles for Application Governance](#) on page 26
- [Application roles for custom tasks](#) on page 26

Application roles for basic functions

NOTE: This application role is available if the Identity Management Base Module is installed.

The following application roles are available to you for the basic functionality in One Identity Manager.

Table 1: Application roles for basic functions

Application role	Description
Administrators	<p>Administrators must be assigned to the Base roles Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Administer application roles for administrators. • Assign employees to administrator application roles. • Add other employees to the Base roles Administrators application role and edit conflicting application roles. • See the main data for the other application roles. • Can use Password Reset Portal to set passwords for selected system users.
Everyone (change)	<p>The Base roles Everyone (change) application role is automatically assigned to every user.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Can edit certain employee main data in the Web Portal. <p>If every user is automatically assigned to a custom permissions group when they log in, then this permissions group can be added to the application role.</p> <p>Members of this application role are determined through a dynamic role.</p>
Everyone (lookup)	<p>The Base roles Everyone (Lookup) application role is automatically assigned to every user.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Obtain read access to objects in the Web Portal. <p>If every user is automatically assigned to a custom permissions group when they log in, then this permissions group can be added</p>

Application role	Description
	<p>to the application role.</p> <p>Members of this application role are determined through a dynamic role.</p>
Employee managers	<p>The Base roles Employee managers application role is automatically assigned to a user if the user is a manager or supervisor of employees, departments, locations, cost centers, business roles, or IT Shops.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Can edit main data for the objects they are responsible for and assign company resources to them. • Can edit new employees added in the Web Portal and edit the main data of their staff. • Can add their staff members to the IT Shop. • Can view their staff compliance rule violations in the Web Portal. • Can create delegations for their staff in Web Portal. • Can see and edit their staff delegations in Web Portal. <p>Members of this application role are determined through a dynamic role.</p>
Birthright Assignments	<p>The Base roles Birthright assignments application role is used to provide birthrights to employees which are provided to establish their working environment. The application roles are allocated all the resources marked for automatic assignment to all employees. All internal employees are assigned to this application role and obtain the resources. Internal employees are found through a dynamic role.</p>
Self-registered employees	<p>All new external employees that have registered themselves in the Web Portal, are assigned to the Base roles Self-registered employees application role. These employees are determined by a dynamic role.</p>

Related topics

- [Custom extension of application role permissions](#) on page 31
- [Application role for the Operations Support Web Portal](#) on page 12

Application role for the Operations Support Web Portal

The Operations Support Web Portal helps you to manage and use your web applications. For more information, see the *One Identity Manager Operations Support Web Portal User Guide*.

NOTE: This application role is only available if the Identity Management Base Module is installed.

The following application roles are available for the Operations Support Web Portal.

Table 2: Application role for the Operations Support Web Portal

Application role	Description
Operations support	Employees that use the Operations Support Web Portal, must be assigned the Base roles Operations support application role. Users with this application role: <ul style="list-style-type: none">• Monitor handling of Job queue processes.• Monitor handling of the DBQueue.• Create passcodes to enable staff to log in to the Password Reset Portal.
Password help desk	Members of the Basic roles Operations support Password help desk application role can reset passwords for other employees in the Operations Support Web Portal.
Synchronization post-processing	Members of the Basic roles Operations support Synchronization post-processing application role are authorized to manage objects in the Operations Support Web Portal that were identified as pending during synchronization.
System administrators	Members of the Base roles Operations support System administrators application role can start and stop processing of the Job queue and the DBQueue in the Operations Support Web Portal.

Application role for Compliance & Security Officers

NOTE: This application role is available if Attestation Module, Compliance Rules Module, or Company Policies Module is installed.

Compliance and security officers must be assigned to the **Identity & Access Governance | Compliance & Security Officer** application role.

Users with this application role:

- View all compliance relevant information and other analysis in the Web Portal. This includes attestation policies, company policies and policy violations, compliance rules, and rule violations and risk index functions.
- Edit attestation policies.

Application role for auditors

NOTE: This application role is available if Attestation Module, Compliance Rules Module or Company Policies Module is installed.

Auditors are assigned to the **Identity & Access Governance | Auditors** application role.

Users with this application role:

- See the Web Portal all the relevant data for an audit.

Application roles for identity audit

NOTE: This application role is available if the Compliance Rules Module is installed.

The following application roles are available for managing compliance rule:

Table 3: Application roles for identity audit

Application role	Description
Administrators	<p>Administrators must be assigned to the Identity & Access Governance Identity Audit Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Enter base data for setting up company policies.• Create compliance rules and assign rule supervisors to them.• Can start rule checking and view rule violations as required.• Create reports about rule violations.• Enter mitigating controls.• Create and edit risk index functions.• Monitor Identity Audit functions.• Administer application roles for rule supervisors, exception approvers and attestors.

Application role	Description
	<ul style="list-style-type: none"> Set up other application roles as required.
Rule supervisors	<p>Rule supervisors must be assigned to the Identity & Access Governance Identity Audit Rule supervisors application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Are responsible for compliance rule content, for example, an auditor or a auditing department. Edit the compliance rule working copies, which are assigned to the application role. Enable and disable compliance rules. Can start rule checking and view rule violations as required. Assign mitigating controls.
Exception approvers	<p>Administrators must be assigned to the Identity & Access Governance Identity Audit Exception approvers application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Edit rule violations in the Web Portal. Can grant exception approval or revoke it in the Web Portal.
Attestors	<p>Attestors must be assigned to the Identity & Access Governance Identity Audit Attestors application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Attest compliance rules and exception approvals in the Web Portal for which they are responsible. Can view main data for these compliance rules but not edit them. <p>NOTE: This application role is available if the module Attestation Module is installed.</p>
Maintain SAP Functions	<p>Administrators must be assigned to the Identity & Access Governance Identity Audit Maintain SAP functions application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Are responsible for SAP function contents. Edit working copies of function definitions for which they are responsible. Define function instances and variables sets for SAP functions.

Application role	Description
	<ul style="list-style-type: none"> Assign mitigating controls. <p>NOTE: This application role is available if the module SAP R/3 Compliance Add-on Module is installed.</p>

Application roles for company policies

NOTE: This application role is available if the Company Policies Module is installed.

The following application roles are available for managing company policies:

Table 4: Application roles for company policies

Application role	Description
Administrators	<p>Administrators must be assigned to the Identity & Access Governance Company policies Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Enter base data for setting up company policies. Set up policies and assign policy supervisors to them. Can calculation policies and view policy violations if required. Set up reports about policy violations. Enter mitigating controls. Create and edit risk index functions. Administer application roles for policy supervisors, exception approvers and attestors. Set up other application roles as required.
Policy supervisors	<p>Policy supervisors must be assigned to the Identity & Access Governance Company policies Policy supervisors application role or another child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Are responsible for the contents of company policies. Edit working copies of company policies. Enable and disable company policies. Can calculation policies and view policy violations if required. Assign mitigating controls.

Application role	Description
Exception approvers	<p>Exception approvers must be assigned to the Identity & Access Governance Company policies Exception approvers application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Edit policy violations. • Can grant exception approval or revoke it.
Attestors	<p>Attestors must be assigned to the Identity & Access Governance Company policies Attestors application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Attest company policies and exception approvals in the Web Portal for which they are responsible. • Can view the main data for these company policies but not edit them. <p>NOTE: This application role is available if the module Attestation Module is installed.</p>

Application roles for attestation

NOTE: This application role is available if the Attestation Module is installed.

The following application roles are available for managing attestation procedures:

Table 5: Application roles for attestation

Application role	Description
Administrators	<p>Administrators are assigned to the Identity & Access Governance Attestation Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Define attestation procedures and attestation policies. • Create approval policies and approval workflows. • Specify which approval procedure to use to find attestors. • Set up attestation case notifications. • Configure attestation schedules. • Enter mitigating controls. • Create and edit risk index functions.

Application role	Description
	<ul style="list-style-type: none"> Monitor attestation cases.
Chief approval team	<p>The chief approver must be assigned to the Identity & Access Governance Attestation Chief approval team application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Approve using attestation cases. Assign attestation cases to other attestors.
Attestors for external users	<p>Attestors for external users must be assigned to the Identity & Access Governance Attestation Attestors for external users application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Attests new, external employees.
Attestation policy owner	<p>Owners of attestation policies must be assigned to a child application role of the Identity & Access Governance Attestation Attestation policy owners application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Are responsible for its content and handle the attestation policies assigned to it. Assign the attestation procedure, approval policy, and calculation schedule. Assign approvers, mitigating controls, and compliance frameworks. Monitor attestation cases.

NOTE: Attestors in charge are determined through approval procedures. Other application roles may be applied here. Application roles for attestors are defined in different module and are available if the Attestation Module is installed.

Application roles for subscribable reports

NOTE: This application role is available if the module Report Subscription Module is installed.

The following application role is available for managing subscribable reports:

Table 6: Application roles for subscribable reports

Application role	Description
Administrators	<p>Administrators must be assigned to the Identity & Access Governance Company policies Report Subscriptions application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Create subscribable reports from existing reports.• Configure report parameters for subscribable reports.• Assign subscribable reports to employees, company structures or IT Shop shelves.• Create custom mail templates for sending subscribed reports by email.

Application roles for management levels

NOTE: This application role is available if the module Identity Management Base Module is installed.

The user must be assigned to the **Identity Management | Management level** application role.

Users with this application role:

- Can view reports and statistics in the Web Portal that are intended for their company's management level.

Application roles for business roles

NOTE: This application role is available if the Business Roles Module is installed.

The following application roles are available for the administration of business roles:

Table 7: Application roles for business roles

Application role	Description
Administrators	<p>Administrators must be assigned to the Identity Management Business roles Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Create and edit business roles.

Application role	Description
	<ul style="list-style-type: none"> • Assign company resources to business roles. • Administrate application roles for role approvers, role approvers (IT), and attestors. • Set up other application roles as required.
Attestors	<p>Attestors must be assigned to the Identity Management Business roles Attestors application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Attest correct assignment of company resource to business roles for which they are responsible. • Can view main data for these business roles but not edit them. <p>NOTE: This application role is available if the module Attestation Module is installed.</p>
Role approver	<p>Approvers must be assigned to the Identity Management Business roles Role approvers application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Are approvers for the IT Shop. • Approve requests from business roles for which they are responsible.
Role approver (IT)	<p>IT role approvers must be assigned to the Identity Management Business roles Role approvers (IT) application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Are IT role approvers for the IT Shop. • Approve requests from business roles for which they are responsible.

Application roles for organizations

NOTE: This application role is available if the Identity Management Base Module is installed.

The following application roles are available for the administration of departments, cost centers and locations:

Table 8: Application roles for organizations

Application role	Description
Administrators	<p>Administrators must be assigned to the Identity Management Organizations Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Set up and edit departments, cost centers, and locations.• Assign company resources to departments, cost centers, and locations.• Administrate application roles for role approvers, role approvers (IT), and attestors.• Set up other application roles as required.
Attestors	<p>Attestors must be assigned to the Identity Management Organizations Attestors application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Attest correct assignment of company resources to departments, cost centers, and locations for which they are responsible.• Can view main data for departments, cost centers, and locations but cannot edit them. <p>NOTE: This application role is available if the module Attestation Module is installed.</p>
Role approver	<p>Role approvers must be assigned to the Identity Management Organizations Role approvers application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Are approvers for the IT Shop.• Approve request from departments, cost centers, and locations for which they are responsible.
Role approver (IT)	<p>IT role approvers must be assigned to the Identity Management Organizations Role approvers (IT) application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Are IT role approvers for the IT Shop.• Approve request from departments, cost centers, and locations for which they are responsible.

Application for employee administrators

NOTE: This application role is available if the module Identity Management Base Module is installed.

The following application role is available for employee administration:

Table 9: Application roles for employees

Application role	Description
Administrators	<p>Employee administrators must be assigned to the Identity Management Employees Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Can edit main data for all employees• Assign managers to employees.• Can assign company resources to employees.• Check and authorize employee main data.• Create and edit risk index functions.• Edit password policies for employee passwords• Delete employee's security keys (WebAuthn)• Can see everyone's requests and delegations and edit delegations in Web Portal.

Application roles for the IT Shop

NOTE: This application role is available if the Identity Management Base Module is installed.

The following application roles are available for the IT Shop administration:

Table 10: Application roles for the IT Shop

Application role	Description
Administrators	<p>Administrators must be assigned to the Request & Fulfillment IT Shop Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Create the IT Shop structure with shops, shelves, customers, templates, and service catalog.

Application role	Description
	<ul style="list-style-type: none"> • Create approval policies and approval workflows. • Specify which approval procedure to use to find attestors. • Create products and service items. • Set up request notifications. • Monitor request procedures. • Administrate application roles for product owners and attestors. • Set up other application roles as required. • Create extended properties for company resources of any type. • Edit the resources and assign them to IT Shop structures. • Assign system entitlements to IT Shop structures.
Product owners	<p>Product owners must be assigned to the Request & Fulfillment IT Shop Product owners application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Approve through requests. • Edit service items and service categories under their management.
Attestors	<p>Attestors must be assigned to the Request & Fulfillment IT Shop Attestors application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Attest correct assignment of company resource to IT Shop structures for which they are responsible. • Attest objects that have service items assigned to them. • Can view main data for these IT Shop structures but not edit them. <p>NOTE: This application role is available if the Attestation Module is installed.</p>
Chief approval team	<p>Chief approvers must be assigned to the Request & Fulfillment IT Shop Chief approval team application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Approve through requests. • Assign requests to other approvers.

NOTE: The approvers responsible are determined through approval procedures. Other application roles may be applied here. Application roles for approvers are defined in different modules and are available there.

Application roles for target systems

NOTE: Application roles are dependent on the target system and are contained in One Identity Manager modules. Application roles are not available until the modules are installed.

The following application roles are available for target system administration:

Table 11: Application roles for target systems

Application role	Tasks
Administrators	<p>Target system administrators must be assigned to the Target systems Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Administer application roles for individual target system types.• Specify the target system manager.• Set up other application roles for target system managers if required.• Specify which application roles for target system managers are mutually exclusive.• Authorize other employees to be target system administrators.• Do not assume any administrative tasks within the target system.
Target system managers	<p>Target system managers must be assigned to the Target systems <target system> application role or a child application role.</p> <p>NOTE: There is at least one application role per target system for target system managers. This application role is available if the target system module is installed.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Assume administrative tasks for the target system.• Create, change, or delete target system objects.• Edit password policies for the target system.• Prepare system entitlements to add to the IT Shop.• Can add employees who have another identity than the Primary identity.• Configure synchronization in the Synchronization Editor and define the mapping for comparing target systems and One Identity Manager.

Application role	Tasks
	<ul style="list-style-type: none"> Edit the synchronization's target system types and outstanding objects. Authorize other employees within their area of responsibility as target system managers and create child application roles if required.
Target system managers for Unified Namespace	<p>Target system managers must be assigned to the Target systems Unified Namespace application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Obtain view of the objects in the connected target systems across all target systems. Can create reports across all target systems. <p>If the users are also target system managers of the basic underlying target systems, you can manage these target systems through the Unified Namespace.</p>

Application roles for Universal Cloud Interface

NOTE: Application roles are available if the Universal Cloud Interface Module is installed. The following application roles are available for managing cloud systems.

Table 12: Application roles for Universal Cloud Interface

Application role	Tasks
Cloud administrators	<p>Cloud administrators must be assigned to the Universal Cloud Interface Administrators application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Manage application roles for the Universal Cloud Interface. Set up other application roles as required. Configure synchronization in the Synchronization Editor and define the mapping for comparing cloud applications and One Identity Manager. Edit cloud application in the Manager. Edit pending, manual provisioning processes in the Web

Application role	Tasks
	<p>Portal and obtain statistics.</p> <ul style="list-style-type: none"> Obtain information about the cloud objects in the Web Portal and the Manager.
Cloud operators	<p>The cloud operators must be assigned to the Universal Cloud Interface Operators application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Edit pending, manual provisioning processes in the Web Portal and obtain statistics.
Cloud auditors	<p>The cloud auditors must be assigned to the Universal Cloud Interface Auditors application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Can view manual provisioning processes in the Web Portal and obtain statistics.

Application role for Privileged Account Governance

NOTE: This application role is available if the module Privileged Account Governance Module is installed.

Table 13: Application role for Privileged Account Governance

Application role	Description
Asset and account owners	<p>Owners of privileged objects, such as PAM assets, PAM asset accounts, PAM directory accounts, PAM asset groups, and PAM account groups must be assigned to an application role under the Privileged Account Governance Asset and account owners application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Make decisions about requesting access requests for privileged objects. Attest the possible user access to these privileged objects.

Application roles for Application Governance

NOTE: This application role is available if the module Application Governance Module is installed.

Table 14: Application roles for Application Governance

Application role	Tasks
Administrators	Administrators must be assigned to the Application Governance Administrators application role. Users with this application role: <ul style="list-style-type: none">• Create new business applications in the Web Portal.• Manage all business applications in the Web Portal.
Owner	The owners of business applications must be assigned to the Application Governance Owners application role. Users with this application role: <ul style="list-style-type: none">• Can edit business applications that they manage in the Web Portal.
Approver	Approvers must be assigned to the Application Governance Approvers application role. Users with this application role: <ul style="list-style-type: none">• Approve requests for business application products.

Application roles for custom tasks

NOTE: This application role is available if the Identity Management Base Module is installed.

The following application roles are available for customer features and tasks.

Table 15: Application roles for custom tasks

Application role	Description
Administrators	Administrators must be assigned to the Custom Administrators application role. Users with this application role: <ul style="list-style-type: none">• Administrate custom application roles.• Set up other application roles for managers if required.

Application role	Description
Manager/supervisor	<p>Managers must be assigned to the Custom Managers application role or a child role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Add custom task in One Identity Manager. • Configure and start synchronization in the Synchronization Editor. • Edit the synchronization's target system types as well as outstanding objects in the Manager. <p>You can use these application roles, for example, to guarantee One Identity Manager user permissions on custom tables or columns. All application roles that you define here must obtain their permissions through custom permissions groups.</p>

Implementing the application roles

IMPORTANT: To use application roles you must add one employee to the **Base roles | Administrators** application role. This employee is the authorized to assigned administrative One Identity Manager application roles to other employees.

Run this task once.

*To initially add an employee to the **Base roles | Administrators** application role.*

1. Log into the Manager as a non role-based administrative user.
2. Select the **Employees > Employees** category.
3. Select the employee to be assigned to the **Base role | Administrators** application role.
4. Select the **Authorize as One Identity Manager administrator** task.

The One Identity Manager user with the **Base roles | Administrators** application role can now add more employees to application roles and edit the application role main data.

NOTE: Once you update the view in the Manager, the **Authorize as One Identity Manager administrator** task is no longer displayed in the task view. That means that the task can only be run when there are no other employees assigned to this application role.

After you have been working with One Identity Manager for a while, it is possible that no more employees are assigned to the **Base roles | Administrators** application role. In this case, proceed as described above in order to reassign an employee to this application role.

Related topics

- [Assigning employees to application roles](#) on page 30
- [Creating and editing application roles](#) on page 28

Creating and editing application roles

To set up your first application roles you need to add an employee to the application role **Base roles | Administrators**. This employee is authorized to add more employees to different administration application roles. For more information, see [Implementing the application roles](#) on page 27.


Administrators can edit child application roles, set up more application roles and assigned employees.

NOTE: To edit the application role, log on to the Manager using a role-based authentication module.

To edit an application role

1. In the Manager in the **One Identity Manager Administration** category, select the Application role.
2. Select the **Change main data** task.
3. Edit the application role's main data.
4. Save the changes.

To create a new application role

1. In the Manager in the **One Identity Manager Administration** category, select the application role under which you want to create a new application role.
2. Click  in the result list.
3. Enter the application role main data.
4. Save the changes.

NOTE: You cannot delete default application roles.

Related topics

- [Main data of application roles](#) on page 29
- [Assigning employees to application roles](#) on page 30
- [Custom extension of application role permissions](#) on page 31
- [One Identity Manager authentication modules](#) on page 68

Main data of application roles

Table 16: Application role properties

Property	Meaning
Application role	Application role name.
Internal name	Empty text field for a internal company identifier
Full name	Full name of application role. Is made up automatically from the application role name and the parent application role.
Parent application role	Application role to which the application role being edited is subordinate.
Department, location, cost center	Additional information for the application role definition. These input fields are only used for information. They do not indicate for which department, cost center or location the application roles are responsible.
Manager	Manager responsible for the application role.
Deputy manager	Deputy manager for the application role.
Permissions group	<p>Permissions group for determining permissions for role-based login. The application role is given the permissions of the associated permissions group. If no permissions group assigned, the application role is obtains the permissions from the parent application role.</p> <p>Administrators can assign the rest of the application roles to custom defined permissions groups. For more information, see Custom extension of application role permissions on page 31.</p> <p>NOTE: Permissions groups for default administrator application roles for cannot be edited.</p>
Description	Text field for additional explanation.
Comment	Text field for additional explanation.
Certification status	<p>Status of the application role's certification. The following values can be selected.</p> <ul style="list-style-type: none">• New: The application role was newly created in the One Identity Manager database.• Certified: The main data of the application role is approved by a manager.• Denied: The application role main data was not approved by a manager.
Block	Specifies whether inheritance for this application role can be

Property	Meaning
inheritance	discontinued. Set this option to prevent company resources being inherited by child application roles. NOTE: Inheritance of application roles can only be discontinued if they are custom application roles.
Dynamic roles not allowed	Specifies whether a dynamic role can be created for the application role.
Spare field no. 01 ... Spare field no. 10	Additional company-specific information. Use the Designer to customize display names, formats, and templates for the input fields.

Assigning employees to application roles

Assigned employees obtain all the permissions of the permission group to which the application role (or a parent application role) is assigned. In addition, employees obtain the company resources assigned to the application role.

If there are no employees directly assigned to an application role, the employees of the parent application role inherit the permissions.


NOTE: The application roles for **Base roles | Everyone (Change)**, **Base roles | Everyone (Lookup)**, **Base roles | Employee Managers**, and **Base roles | Birth-right Assignments** are automatically assigned to employees. Do not make any manually assignments to these application roles.

To assign employees to an application role

1. In the Manager, select an application role in the **One Identity Manager Administration** category.
2. Select the **Assign employees** task.
3. In the **Add assignments** pane, add employees.

TIP: In the **Remove assignments** pane, you can remove assigned employees.

To remove an assignment

- Select the employee and double-click .
4. Save the changes.

Related topics

- [Creating and editing dynamic roles for application roles](#) on page 32

Custom extension of application role permissions

For role-based login, application roles must link to a permissions group in which permissions for One Identity Manager are defined. The application role is given the permissions of the associated permissions group. If no permissions group assigned, the application role obtains the permissions from the parent application role.

Some of the default application roles are already assigned permissions groups. These permissions groups have the permissions for the tables and columns and are equipped with menu items, forms, tasks, and program functions, which allow the application data to be edited in the Manager and in the Web Portal.

You can assign customized permissions groups to application roles so that the permissions for application roles meet your company requirements. You need to ensure that your custom permissions groups contain all the write permissions of the default permissions groups for these application roles. This allows users with these application roles to use all default One Identity Manager functionality.

NOTE: You can simplify grouping of permissions by using hierarchical linking of permissions groups. Permissions from hierarchical permissions groups are inherited from top to bottom. That means that a permissions group contains all the permissions belonging parent permissions groups.

Proceed as follows:

1. In the Designer, create a new permissions group .
NOTE: Set the **Only use for role-based authentication** option for the permissions group.
2. In the Designer, make the new permissions group dependent on the default permissions group of the application role. Assign the default permissions group as a parent permissions group. This means the newly defined permissions group inherits the properties of the default permissions group.
3. In the Designer, grant additional edit permissions for menu items, forms, tables, or columns.
4. In the Manager, assign the new permissions group to the application role.

A user who logs in to the Manager or to the Web Portal with an application role changed in this way receives – in addition to the default privileges of this application role – the custom permissions.

Related topics

- [Main data of application roles](#) on page 29
- [Granting One Identity Manager schema permissions through permissions groups](#) on page 36

Creating and editing dynamic roles for application roles

Use this task to assign employees to an application role through dynamic roles. For detailed information about using dynamic roles, see the *One Identity Manager Identity Management Base Module Administration Guide*.

NOTE: The task **Create dynamic role** is only available for application roles that do not have the option **Dynamic roles not allowed** set.

To create a dynamic role for the application role

1. In the Manager in the **One Identity Manager Administration** category, select the application role.
2. Select the **Create dynamic role** task.
3. Enter the required main data. The following applies to dynamic roles for application roles:
 - **Object class:** Select **Employee**.
 - **Application role:** This data is preset with the selected application role. If these objects fulfill the dynamic role conditions, they become members in the application role.
 - **Dynamic role:** The dynamic role name is made up of the object class and the full name of the application role by default.
4. Save the changes.

To edit a dynamic role

1. In the Manager in the **One Identity Manager Administration** category, select the application role.
2. Select the **Application role overview** task.
3. In the overview form, click the dynamic role name in the **Dynamic roles** form element.
4. Select the **Change main data** task.
5. Edit the dynamic role.
6. Save the changes.

Related topics

- [Main data of application roles](#) on page 29

Specifying mutually exclusive application roles

It is possible that employees cannot own certain system roles at the same time. Thus, for example, exception approvers for rule violations may not be rule supervisors at the same time. To implement this behavior, you can specify mutually exclusive application roles. Then you cannot assign these application roles to the same person anymore.

NOTE: Only system roles, which are defined directly as conflicting application roles, cannot be assigned to the same employee. Definitions made on parent or child application roles do not effect the assignment.

To configure inheritance exclusion

- In the Designer, set the **QER | Structures | ExcludeStructures** configuration parameter and compile the database.

To specify inheritance exclusion for application roles

1. In the Manager in the **One Identity Manager Administration** category, select the application role for which you want to define an inheritance exclusion.
2. Select the **Edit conflicting application roles** task.
3. In the **Add assignments** pane, assign application roles that are mutually exclusive to the selected system role.
- OR -
In the **Remove assignments** pane, remove the application roles that are no longer mutually exclusive.
4. Save the changes.

Assigning subscribable reports to application roles

Use this task to assign subscribable reports to an application role. All employee in this application role can subscribe to reports in the Web Portal. For more information about subscribable reports, see the *One Identity Manager Report Subscriptions Administration Guide*.

NOTE:

- This function is only available if the Report Subscription Module is installed.
- The task is only available if a permissions group is assigned to the application role (or a parent application role).


- Subscribable reports cannot be assigned to the **Base roles | Employee Managers**, the **Base roles | Everyone (Lookup)**, or the **Base roles | Everyone (Change)** application role.

To assign subscribable reports to an application role

1. In the Manager, select an application role in the **One Identity Manager Administration** category.
2. Select the **Assign subscribable reports** task.
3. In the **Add assignments** pane, assign reports.

TIP: In the **Remove assignments** pane, you can remove report assignments.

To remove an assignment

- Select the report and double-click .
4. Save the changes.

Assigning extended properties to application roles


Extended properties are meta objects, such as operating codes, cost codes, or cost accounting areas that cannot be mapped directly in One Identity Manager. For detailed information about using extended properties, see the *One Identity Manager Identity Management Base Module Administration Guide*.

To specify extended properties for an application role

1. In the Manager, in the **One Identity Manager Administration** category, select the Application role.
2. Select the **Assign extended properties** task.
3. In the **Add assignments** pane, assign extended properties.

TIP: In the **Remove assignments** pane, you can remove assigned extended properties.

To remove an assignment

- Select the extended property and double-click .
4. Save the changes.

Generating assignment resources for application roles

It is possible to create assignment resources for individual application roles. This means you can limit assignment resources to individual application roles in the Web Portal. When the assignment resource is requested, it is no longer necessary to select the application role as well. The application role is automatically a part of the assignment request. For detailed information about assignment requests, see the *One Identity Manager IT Shop Administration Guide*.

To limit an assignment resource to one application role

1. In the Manager in the **One Identity Manager Administration** category, select the Application role.
2. Select the **Create assignment resource** task.

This starts a wizard that takes you through the steps for adding an assignment resource.

Reports about application roles

One Identity Manager makes various reports available containing information about the selected base object and its relations to other One Identity Manager database objects. The following reports are available for application roles.

Table 17: Reports about application roles

Report	Description
Overview of all assignments	This report identifies all departments, cost centers, locations, business roles or IT Shop structures in which employees from the selected application role are also members. For detailed information about analyzing role memberships, see the <i>One Identity Manager Identity Management Base Module Administration Guide</i> .
Show historical memberships	This report lists all members of the selected application role and the length of their membership.

Granting One Identity Manager schema permissions through permissions groups

Permissions for accessing tables and columns of the One Identity Manager schema are themselves mapped in the schema through permissions groups. You can assign permissions groups to system users and to application roles.

Permissions groups are also used to control access to parts of the user interface, such as, menu items, forms, tasks, and program functions. When a user logs in to One Identity Manager tools, all available menus, forms, and methods are loaded depending on the system user's permissions groups, displaying a user interface customized for this system user. For more detailed information about editing the user interface, see the *One Identity Manager Configuration Guide*.

One Identity Manager provides permissions groups and system users with a predefined user interface and special permissions for One Identity Manager schema's tables and columns. These predefined configurations are maintained by the schema installation and cannot be edited apart from a few properties.

Detailed information about this topic

- [Predefined permissions groups and system users](#) on page 37
- [Rules for determining the valid permissions for tables and columns](#) on page 39
- [Editing permissions groups](#) on page 42
- [Editing system users](#) on page 47
- [Permissions for tables and columns](#) on page 53
- [Managing permissions to program features](#) on page 63
- [Displaying permissions for objects](#) on page 60
- [Displaying permissions for the current user](#) on page 61
- [Assigning role-based permissions groups to an applications](#) on page 61

Related topics

- [One Identity Manager application roles](#) on page 8
- [One Identity Manager authentication modules](#) on page 68

Predefined permissions groups and system users

One Identity Manager provides permissions groups and system users with a predefined user interface and special permissions for One Identity Manager schema's tables and columns. These predefined configurations are maintained by the schema installation and cannot be edited apart from a few properties.

Table 18: Predefined permissions groups

Permissions group	Description
Permissions group QBM_BaseRights	The QBM_BaseRights permissions group defines the base rights that are required for a system user to log in to the One Identity Manager tools. This permissions group is always assigned implicitly.
Permission group VID_Features	The VID_Features permissions group covers all program functions required for starting the One Identity Manager tools. The permissions group covers additional program functions for running special functions in One Identity Manager.
Permission group VID_View	The VI_View permissions group has viewing permissions for all tables and columns that map application data. NOTE: Assign viewing permissions of custom schema extensions to the permissions group.
Permission group VID_Everyone	The VI_Everyone permissions group is assigned to elements of the overview forms that use links to the corresponding menu items. These permissions groups also provide functions for Web Portal users. NOTE: Assign the permissions group to your custom system users such that the overview form is fully displayed to the users.
Permissions groups for One Identity Manager application data	The permissions groups have permissions on the tables and the columns that map application data. These permissions groups are equipped with menu items, forms, tasks, and program functions which allows the application data to be edited with, for example, the Manager.

Permissions group	Description
Permissions groups for One Identity Manager system data	<p>The permissions groups have permissions on the tables and the columns that map the One Identity Manager's system data. These permissions groups are equipped with menu items, forms, tasks, and program functionality which allows the application data to be edited, for example, with Designer editors.</p> <p>The vid permissions group has all edit permissions for the system configuration with the Designer.</p>
Role-based permissions group VI_4_ALLUSER	The VI_4_ALLUSER permissions group provides the base permissions as well as menu items, forms, tasks, and program functions to enable the application data to be edited with the Manager and the Web Portal. This permissions group is always assigned implicitly.
Role-based permissions group VI_4_ADMIN_LOOKUP	<p>The vi_4_ADMIN_LOOKUP permissions group has the viewing permissions for all tables and columns of the application data.</p> <p>NOTE: Assign viewing permissions of custom schema extensions to the permissions group.</p>
Role-based permissions group QER_OperationsSupport	The QER_OperationsSupport permissions group has special permissions for working with the Operations Support Web Portal. The permissions group is assigned to the OperationsSupportWebPortal application. The permissions of the permissions group apply only in the Operations Support Web Portal.
Role-based permissions groups	Role-based permissions groups have permissions on the tables and the columns that map application data. These permissions groups are equipped with menu items, forms, tasks, and program functionality which allow the application data to be edited with the Manager and the Web Portal. These permissions groups are linked to the One Identity Manager application roles and simplify administration of access permissions in the One Identity Manager role model.

Table 19: Predefined system users

System users	Description
Dynamic system user	Dynamic system users are used for logging into One Identity Manager tools with role-based authentication modules. First, the employee memberships in the One Identity Manager application roles are determined during login. Assignments of permissions groups to One Identity Manager application roles are used to determine which permissions groups apply to the employee. A dynamic system user is determined from these permissions groups that will be used for the employee's login.

System users	Description
System user sa	The sa system user is used exclusively by the One Identity Manager Service. This system user is not assigned to a permissions group but has all the permissions, tasks, and program functionality.
System user viadmin	<p>The viadmin system user is the default system user in One Identity Manager. This system user can be used to compile and initialize the One Identity Manager database and for the first user login to the administration tools.</p> <p>IMPORTANT: Do not use the viadmin system user in a live environment. Create your own system user with the appropriate permissions.</p> <p>The system user has all of the specified permissions and the complete user interface. The system user implicitly receives the authorizations and user interface parts of the custom permissions groups. The system user has the permission to set up an employee as a One Identity Manager administrator for the role-based login. The system user is not a member of the application role themselves.</p>
System user Synchronization	The Synchronization system user has the necessary permissions to set up and run target system synchronizations using an application server.
System user viHelpdesk	The viHelpdesk system user has the necessary permissions and the user interface to use the Manager to access One Identity Manager helpdesk resources.

Related topics

- [Dependencies between permissions groups](#) on page 43
- [Editing permissions groups](#) on page 42
- [Creating system users](#) on page 48
- [Dynamic system user](#) on page 52

Rules for determining the valid permissions for tables and columns

When a system user is used to log into the system, the permissions for the objects that are currently in effect, are determined on the basis of the permissions groups. The following rules are used to determine the resulting permissions:

- Permissions from hierarchical permissions groups are inherited from top to bottom. That means that a permissions group contains all the permissions belonging parent permissions groups.
- The number of objects is determined first for hierarchical permissions groups. Column permissions are decided afterward. In some cases, this results in more permissions than are defined on individual permissions groups.
- A system user receives a permission when are least one of its permissions groups has the permission (directly or inherited).
- The limiting permissions conditions for all the system user's permissions groups are grouped together and used to determine a valid condition for each permission for viewing, editing, inserting, and deleting an object.
- Fixed viewing permissions for the One Identity Manager schema's system data are granted by the system, which are sufficient for logging a system user into the administration tools.
- A system user with read-only permissions only obtains viewing permissions to objects irrespective of any other permissions.
- If permissions are granted on a table for inserting, editing, or deleting, viewing permissions are implicit.
- If permissions are granted on a column for inserting, editing, or deleting, viewing permissions are implicit.
- If permissions are granted for a table, then viewing permissions are implicitly granted on the primary key column of the table.
- If viewing permissions are granted on a primary key column as a minimum, then viewing permissions are implicitly granted for the referenced table, the primary key column, and the columns that are necessary in the referenced table for viewing according to the defined display pattern.
- Columns that need to be in a defined display pattern in the table are given implicit viewing permissions.
- Permissions for database views of the **Proxy** type also apply to the underlying tables.
- For database views of the **ReadOnly** type, only the viewing permissions apply irrespective of other permissions.
- If a table or column is disabled due to preprocessor conditions, permissions are not determined for those tables and columns. The table or column is considered not to exist.
- If a permissions group is disabled due to preprocessor conditions, permissions are not taken into account for this permissions group. The permissions group is considered not to exist.

Example: Grouping permissions using permissions groups

The following example shows how to group permissions if the user is directly assigned in permissions groups and the permissions groups are not connected hierarchically.

A system user obtains permissions to the ADSAccount table through different permissions groups.

Permissions group	Viewable	Editable	Insertable	Deletable
A	1	1	1	1
B	0	0	0	0

In addition, it is granted permissions to the LDAPAccount table through these permissions groups.

Permissions group	Viewable	Editable	Insertable	Deletable
A	1	0	0	0
B	1	1	1	0

Therefore, the system user has effectively the following permissions:

Table	Viewable	Editable	Insertable	Deletable
ADSAccount	1	1	1	1
LDAPAccount	1	1	1	0

Example: Limiting conditions

A system user obtains viewing permissions to the Person table through different permissions groups.

Permissions group	Viewing condition	Viewing on columns
A		Lastname
B	Lastname like 'B%'	Lastname, Firstname, Entrydate

Permissions group	Viewing condition	Viewing on columns
C	Lastname like 'Be%'	Lastname, Firstname, Gender
D	Lastname like 'D%'	Lastname

This results in the following permissions for the individual employee objects.

Person.Lastname	Visible Columns
Smith	Lastname
Bishop	Lastname, Firstname, Entrydate
Bennett	Lastname, Firstname, Gender
Dreyer	Lastname

Editing permissions groups

One Identity Manager provides permissions groups with a predefined user interface and special permissions for One Identity Manager schema's tables and columns. In certain isolated cases, it may be necessary to define custom permissions groups. You need custom permissions groups, for example, if:

- The default permissions groups grant too many permissions
- Selected default permissions groups are to be grouped to form a new permissions group
- Additional role-based permissions groups are required for the custom application roles
- Permissions for custom adjustments such as schema extensions, forms, or menu structures.

When the One Identity Manager database is installed using the Configuration Wizard, custom permissions groups that you can use are already created.

- For non role-based login, the **CCCViewPermissions** and **CCCEditPermissions** permission groups are created. Administrative system users are automatically added to these permissions groups.
- For role-based login, the **CCCViewRole** and **CCCEditRole** permission groups are created.

In the Designer, permissions groups are managed in the **Permissions > Permissions groups** category. Here you will find an overview of edit permissions and user interface

components that are assigned to individual permissions groups. In addition, the system users are displayed to which the permissions groups are assigned.

Use the Designer to create and edit permissions groups with the User & Permissions Group Editor. The User & Permissions Group Editor displays the permissions groups in their hierarchy. Each permissions group is represented by a permissions group element. Each permissions group element has a tooltip. The contents of the tooltip is made up of the name and description of the permissions group.

You can run the following tasks:

- Edit permissions group main data
- Define new dependencies between permissions groups
- Copy permissions groups
- Create new permissions groups

Related topics

- [Predefined permissions groups and system users](#) on page 37
- [Permissions group dependencies](#) on page 44
- [Copying permissions groups](#) on page 45
- [Creating permissions groups](#) on page 46
- [Permissions group properties](#) on page 47
- [Managing permissions to program features](#) on page 63

Dependencies between permissions groups

By structuring permissions groups hierarchically, permissions and user interface components can be passed down from one permissions group to another permissions group. This means that inheritance is top down within the hierarchy.

The following applies to permissions group dependencies:

- A role-based permissions group can inherit from role-based permissions groups and non role-based permissions groups.
- A non role-based permissions group can inherit from non role-based permissions groups. A non role-based permissions group must not inherit from role-based permissions groups.

Example:

Two permission groups are defined with the following permissions and user interface components.

Permissions group	Permissions	User interface
A	Viewable	Menu structures and forms
B	Editable	Task definitions

Permissions group B is assigned below permissions group A in the hierarchy and inherits from permissions group A. Consequently, a user of permissions group B has access to the viewing permissions and editing permissions as well as the menu structure, forms, and task definitions.

Related topics

- [Permissions group dependencies](#) on page 44

Permissions group dependencies

You edit dependencies between permissions groups in the hierarchical view of the User & Permissions Group Editor. Permissions groups that are higher up in the hierarchy are displayed further to the right in the User & Permissions Group Editor's hierarchical. When a permissions group is selected in the hierarchical view, dependencies to other permissions groups are marked in color thus showing the direction of inheritance.

Figure 1: Visual of the permissions group hierarchy (inheritance from right to left)



Table 20: Meaning of colors in the hierarchical representation

Color	Meaning
Blue	The selected permissions group.
Purple	This permissions group is a child of the selected permissions group and directly inherits from the selected permissions group.
Light purple	This permissions group inherits indirectly from the selected permissions group over the hierarchy.
Red	This permissions group is a child of the selected permissions group and directly inherits from the selected permissions group.
Light	This permissions group passes inheritance indirectly to the selected permis-

Color	Meaning
red	sions group over the hierarchy.
Green	This permissions group does not inherit or pass inheritance to the selected permissions group.

To specify dependencies of a permissions group

1. In the Designer, select the **Permissions > Permissions groups** category.
2. Select the permissions group and start the User & Permissions Group Editor using the **Edit permissions group** task.
3. In the hierarchical view of the permissions groups, select the permissions group and run one of the following actions.
 - Select the **Inherit permissions from** context menu and select the permissions groups from which the selected permissions group is to inherit.
 - Select the **Permissions inherited by** context menu and select the permissions groups to be included in the selected permissions group. Child permissions groups inherit permissions from the selected permissions group.
4. Select the **Database > Save to database** and click **Save**.

Copying permissions groups

The User & Permissions Group Editor provides a wizard for copying permissions and the user interface of an existing permissions group to a new permissions group.

To copy a permissions group

1. In the Designer, select the **Permissions > Permissions groups** category.
2. Select the permissions group you want to copy and start the User & Permissions Group Editor with the **Edit permissions group** task.
3. Select the **Permissions groups > Copy permissions group** menu item.
4. On the start page of the wizard for copying permissions groups, click **Next**.
5. On the **Select permissions group** page, enter the following information:
 - **Select permissions group to copy:** The permissions group is pre-selected.
 - **Copy name:** Name of the new permissions group. A name suggestion is already entered that you can modify. Ensure that the permissions group name begins with the prefix **CCC**.
6. On the **Select copy options** page, specify which permissions group relations are to be copied. You can select multiple options. The following copy options are available.

Table 21: Copy options for permissions groups

Option	Description
Permissions	Enable this option to copy the table permissions and column permissions of the selected permissions group to the new permissions group.
User interface	Enable this option to copy the menu items, the forms and the task definitions of the selected permissions group to the new permissions group.
System user	Select this option if the system user should be copied to the new permissions group. NOTE: Predefined system users are not included in the new permissions group.

7. To start compiling, click **Next**.
The copying process may take some time.
8. The **Copy permissions group** page shows the individual copy steps and any error messages. If the copy action is complete, click **Next**.
9. To end the wizard, click **Finish** on the last page.

Related topics

- [Creating permissions groups](#) on page 46
- [Permissions group properties](#) on page 47
- [Permissions group dependencies](#) on page 44
- [Adding system users to permission groups](#) on page 50
- [Permissions for tables and columns](#) on page 53

Creating permissions groups

To create a permissions group

1. In the Designer, select the **Permissions** category.
2. Start the User & Permissions Group Editor with the **Show / edit permissions group** task.
3. Add a new permissions group using the **Permissions groups > New** menu item.
4. Edit the main data of the permissions group.
5. Select the **Database > Save to database** and click **Save**.

Related topics

- [Copying permissions groups](#) on page 45
- [Permissions group properties](#) on page 47
- [Permissions group dependencies](#) on page 44
- [Adding system users to permission groups](#) on page 50

Permissions group properties

Table 22: Properties of a permissions group

Property	Description
Permissions group	Name of the permissions group. Label custom permission groups with the prefix CCC .
Description	Detailed description of the permissions group's purpose.
Remarks	Text field for additional explanation.
Preprocessor condition	You can add a preprocessor condition to permissions groups. This means that the permissions group is only effective when the condition is met.
Permissions group binary pattern	The permissions group binary pattern is used to calculate effective system user permissions. It is provided by the DBQueue Processor.
Only use for role-based authentication	This group includes permissions, form assignments, menu items and program functions for role-based authentication. The permissions group can be assigned to One Identity Manager application roles and is assigned to dynamically determined system users. A direct assignment to non-dynamic system user is not permitted. NOTE: This function is available if the Identity Management Base Module is installed.

Related topics

- [Copying permissions groups](#) on page 45
- [Creating permissions groups](#) on page 46

Editing system users

One Identity Manager provides various system users whose permissions are matched to the various tasks. Create your own system users if required. Add the system users to

permissions groups, thereby granting the system users permissions for the tables and columns of the One Identity Manager schema and make the user interface available.

The system user's effective permissions that are found are not saved in the One Identity Manager schema, but are determined when logging into One Identity Manager tools and then they are loaded.

When installing the One Identity Manager database using the Configuration Wizard, create an administrative system user that is added to non role-based permissions groups and receives all the permissions of the **viadmin** default system user.

In the Designer, system users are displayed in the **Permissions > System users** category. This shows you an overview of the permissions groups that are assigned to each individual system user. Use the Designer to create and edit your system user in the User & Permissions Group Editor.

You can run the following tasks:

- Create new system users, such as an administrative system users or system users for service accounts
- Configure password settings for system users
- Add system users to permission groups
- Determine which employees use a system user

Related topics

- [Predefined permissions groups and system users](#) on page 37
- [Creating system users](#) on page 48
- [System users' passwords](#) on page 49
- [System user properties](#) on page 49
- [Adding system users to permission groups](#) on page 50
- [Which employees use the system user?](#) on page 52
- [Dynamic system user](#) on page 52

Creating system users

NOTE: You can create an administrative system user in User & Permissions Group Editor using the **Create administrator** menu. Administrative system users are automatically added to all non role-based permissions groups.

To create a new system user

1. In the Designer, select the **Permissions** category.
2. Start the User & Permissions Group Editor with the **Show / edit permissions group** task.
3. Add a new system user using the **User > New** menu item.

4. Edit the system user's main data.
5. Add the system user to permissions groups.
6. Select the **Database > Save to database** and click **Save**.

Related topics

- [Predefined permissions groups and system users](#) on page 37
- [System users' passwords](#) on page 49
- [System user properties](#) on page 49
- [Adding system users to permission groups](#) on page 50
- [Dynamic system user](#) on page 52
- [Which employees use the system user?](#) on page 52
- [One Identity Manager authentication modules](#) on page 68

System users' passwords

The **One Identity Manager password policy** is used for logging in to One Identity Manager with a system user. This password policy defined the settings for the system user passwords (DialogUser.Password and Person.DialogUserPassword) as well as the passcode for a one time log in on the Web Portal (Person.Passcode).

If necessary, adjust the password policy to your requirements in the Designer. For detailed information about editing password policies, see *One Identity Manager Operational Guide*.

NOTE: The **One Identity Manager password policy** is marked as the default policy. This password policy is applied if no other password policy can be found for employees, user accounts or system users.

To prevent passwords expiring for service accounts, for example, in the Designer, you can enable the **Password never expires** (DialogUser.PasswordNeverExpires) option for the respective system users.

Related topics

- [System user properties](#) on page 49

System user properties

Table 23: Properties of a system user

Property	Description
System users	Name of the system user for logging in to the administration tools.

Property	Description
Password and password confirmation	Password with which the system logs into the administration tools.
Password last changed	Date of last password change.
Password never expires	Specifies whether the password never expires. Enable the option for service accounts, for example, to prevent the password from expiring. This option overwrites the maximum age of the password.
Remarks	Text field for additional explanation.
Read-only	Set the option if a system user is a member in several permissions groups, but has read-only permissions for the objects. This overrides all edit permissions that the system user is granted through memberships in permission groups.
Logins	Logins with which the system user can log in to the One Identity Manager tools. Enter the login in the form: Domain\User. This information is required if the Account based system user authentication module is used to log into the One Identity Manager tools.
Administrative user	Specifies whether this is an administrative system user. Administrative system users are automatically added to all non role-based permissions groups. NOTE: You can create an administrative system user in the Designer with the User & Permissions Group Editor using the Create administrator menu.
Service account	Specifies whether this is a system user that is used by a service account. This system user is not assigned to a permissions group but has all the permissions, tasks, and program functionality.
External password management	Specifies whether the system user password is determined by an external password management system. You cannot change the password in One Identity Manager. The determination of the system user password must be customized.

Related topics

- [Creating system users](#) on page 48
- [System users' passwords](#) on page 49

Adding system users to permission groups

Add the system users to permissions groups, thereby granting permissions for the tables and columns of the One Identity Manager schema and make the user interface available.

NOTE:

- You cannot add system users to role-based permissions groups. Dynamic system users are calculated for role-based login.
- Administrative system users are automatically added to all non role-based permissions groups.
- The **QBM_BaseRights** permissions group defines the base rights that are required for a system user to log in to the One Identity Manager tools. This permissions group is always assigned implicitly.
- The **viadmin** system user has all of the specified permissions and the complete user interface. The system user implicitly receives the authorizations and user interface parts of the custom permissions groups.

A system user's memberships in permissions groups are displayed in the Designer in the User & Permissions Group Editor. Use the **Options > Display permissions group inheritance** menu to specify whether to display the direct and inherited memberships of permissions groups for a system user.

Figure 2: Memberships of a system user in permissions groups




Table 24: Meaning of icons in the hierarchical display

Icon	Meaning
	The selected system user is not assigned to this permissions group.
	The selected system user is assigned to this permissions group.
	The selected system user is indirectly assigned to this permissions group.
	The selected system user is directly and indirectly assigned to this permissions group.

To assign a system user to a permissions group

1. In the Designer, select the **Permissions > System user** category.
2. Select a system user and start the User & Permissions Group Editor with the **Edit system user** task.
3. In the hierarchical view, select the permission group. By clicking on the icon, you add or delete the selected system user to or from a permissions group.
4. Select the **Database > Save to database** and click **Save**.

TIP: To assign a system user to several permissions groups, use the **User > Permissions groups** menu.

Related topics

- [Dynamic system user](#) on page 52

Which employees use the system user?

Employees obtain a system user direct through their main data or dynamically through their One Identity Manager applications roles.

To display which employees are assigned to a system user

1. In the Designer, select the **Permissions > System user** category.
2. Select a system user and start the User & Permissions Group Editor with the **Edit system user** task.
3. Select the **View > One Identity Manager employees** menu item.

| **NOTE:** You cannot change the assignments in this view.

Dynamic system user

Dynamic system users are used for logging into One Identity Manager tools with role-based authentication modules. First, the employee memberships in the One Identity Manager application roles are determined during login. Assignments of permissions groups to One Identity Manager application roles are used to determine which permissions groups apply to the employee. A dynamic system user is determined from these permissions groups that will be used for the employee's login.

| **NOTE:** You cannot edit dynamic system users. If no role-based logins of employees who use dynamic system users are performed for some time, you should delete the dynamic system users for performance reasons. A new dynamic system user is created during the next role-based employee login.

To delete system users

- In the Designer, enable the **Common | DynamicUserLifetime** configuration parameter and enter the maximum retention period in days for dynamic system users.

If the configuration parameter is set, dynamic system users, whose retention period has expired, are deleted from the database as part of the daily maintenance tasks.

Permissions for tables and columns

In the Designer, you can edit permissions using the Permissions Editor. You can also simulate the permissions for the individual system users in the Permissions Editor.

With the Permissions Editor, you can:

- Grant permissions for custom tables and custom columns to custom permissions groups
- Grant permissions for predefined tables and predefined columns in the One Identity Manager schema to custom permissions groups
- Grant permissions for custom tables and custom columns to predefined permissions groups

Permissions of predefined permissions groups for predefined tables and predefined columns of the One Identity Manager schema cannot be changed

For custom schema extensions, use the Schema Extension program to specify permissions groups. A permissions group is given read and write permissions as well as a permissions group with read-only permissions. This make initial access to the custom schema extensions possible with the One Identity Manager administration tools.

Detailed information about this topic

- [Rules for determining the valid permissions for tables and columns](#) on page 39
- [Displaying permissions of a permissions group](#) on page 53
- [Displaying permissions for tables](#) on page 54
- [Editing table permissions](#) on page 55
- [Editing column permissions](#) on page 56
- [Copying table permissions and column permissions](#) on page 57
- [Simulating permissions for system users](#) on page 58

Displaying permissions of a permissions group

To display all permissions for a permission group

1. In the Designer, select the **Permissions** category.
2. Start the Permissions Editor using the **Edit permissions** task.
3. In the Permissions Editor toolbar in the **Permissions group** menu, select the permissions group whose permissions you want to display.

The tables and columns of the One Identity Manager schema and the permissions of the selected permissions group are displayed in the upper area of Permissions Editor. Use the following Permissions Editor options to adjust the layout.

- To display tables with permissions first, enable the **Options > Permissions** sort order menu.
- To display disabled tables and columns, enable the **Options > Show disabled tables** menu.
- To use the display names of the tables and columns, enable the **Options > Display name** menu.
- To limit the display of the tables, use the **Show system tables**, **Show non-system tables**, and **Show all tables** menu items in the **Options** menu. Alternatively, use the **Define filter** or **Manage filters** menu items to define your own user-defined filters for displaying the tables and columns.

For more information about working with user-defined filters in the Designer, see *One Identity Manager User Guide for One Identity Manager Tools User Interface*.

Displaying permissions for tables

In the Permissions Editor, the **Summary of all permissions** view displays the permissions groups that have permissions for the selected column. The permissions in this view cannot be edited.

NOTE: To display the **Summary of all permissions** view, go to the Permissions Editor and enable **View > Object permissions** menu. The view is displayed in the lower area of the Permissions Editor.

To display all permissions for a table and its columns

1. In the Designer, select the table in the **Permissions > By tables** category.
2. Start the Permissions Editor using the **Edit permissions for table** task.

The **Summary of all permissions** view displays the permissions groups that have permissions for the selected table.

TIP: To display a permissions filter completely, click a condition in the view.

3. (Optional) To display all the column permissions, open the table entry in the upper part of the Permissions Editor and select a column.

The **Summary of all permissions** view displays the permissions groups that have permissions for the selected column.

Editing table permissions

Use the table permissions to grant permissions to display, insert, edit, and delete the objects. You can define conditions to further limit the permissions for the objects. You can use the conditions, for example, to link the editability of the employees to their last names. For instance, users can be given read-only access to the employees whose last names begin with A-F, whereas they can edit employees with last names beginning with G-Z.

NOTE: Permissions are always edited in the Permissions Editor for the permissions group that you selected in the Permissions Editor toolbar in the **Permissions group** menu. If you wish to grant permissions for another permissions group, first select this permissions group in the menu and then edit the permissions.

To edit the table permissions for a permissions group

1. In the Designer, select the **Permissions** category.
2. Start the Permissions Editor using the **Edit permissions** task.
3. In the Permissions Editor toolbar in the **Permissions group** menu, select the permissions group for which you want to grant the permissions.
4. Select the table at the top of the Permissions Editor.

TIP: Use **Shift + select** or **Ctrl + select** to select multiple tables.

5. In the **Permissions** section, edit the permissions for the permissions group.
 - To insert new permissions, select the **New** context menu and enable the associated check boxes. Grant the following permissions:
 - **Viewable:** The table data is displayed.
 - **Insertable:** New data can be added to the table.
 - **Editable:** Table data can be edited.
 - **Deletable:** Table data can be deleted

NOTE: If you grant the **Insertable**, **Editable**, or **Deletable** permissions, the **Viewable** permission is also granted.

- To withdraw permissions, disable the associated checkbox.
 - Use the **Delete** context menu, to withdraw all permissions from a table.
6. (Optional) To specify other conditions for table permissions, go to the lower part of the Permissions Editor and switch to the **Group permissions for table** view and select the **Permissions filter** tab.

NOTE: You can only define permissions filters for the tables that map application data.

- Enter the conditions as valid WHERE clauses for database queries. You can enter the following permissions filters.
 - **Viewing Condition:** Limiting condition for displaying data sets.
 - **Edit condition:** Limiting condition for editing data sets.

- **Insert condition:** Limiting condition for inserting data sets.
- **Deletion condition:** Limiting condition for deleting data sets.

Example: Permissions filter

A user should be able to see all employees, but only edit the employees whose last names begin with B. Specify the limiting edit condition as follows, for example:

```
LastName like 'B%'
```

TIP: Use the **SQL check** button to test the condition. This checks the syntax. The number of objects that match the condition is returned.

7. Select the **Database > Save to database** and click **Save**.

Related topics

- [Editing column permissions](#) on page 56
- [Copying table permissions and column permissions](#) on page 57

Editing column permissions

IMPORTANT:

- If you grant permissions to columns, you must also grant the permissions to the tables. For example, a column is only viewable if the table is also viewable.
- To insert objects into a table, the **Insert** permission is required at least for the mandatory fields in the table.
- If you grant **Insert** or **Edit** permissions, **View** permissions are also granted.
- Column definition allows you to use scripts to conditionally display or edit a column. For example, in this way you can control whether or not a column, on a main data form in the Manager, is displayed or can be edited only if another column has a specific value. The script does not change the user's permissions but simply the behavior if the object is loaded in one of the One Identity Manager tools. For more information about editing column definitions, see the *One Identity Manager Configuration Guide*.

NOTE: Permissions are always edited in the Permissions Editor for the permissions group that you selected in the Permissions Editor toolbar in the **Permissions group** menu. If you wish to grant permissions for another permissions group, first select this permissions group in the menu and then edit the permissions.

To edit column permissions for a permissions group

1. In the Designer, select the **Permissions** category.
2. Start the Permissions Editor using the **Edit permissions** task.
3. In the Permissions Editor toolbar in the **Permissions group** menu, select the permissions group for which you want to grant the permissions.
4. Select the table at the top of the Permissions Editor and select the column.
TIP: Use **Shift + select** or **Ctrl + select** to select multiple columns.
5. In the **Permissions** section, edit the permissions for the permissions group.
 - To insert new permissions, select the **New** context menu and enable the associated check boxes. Grant the following permissions:
 - **Viewable:** The column is displayed.
 - **Editable:** The value in the column can be changed.
 - **Insertable:** The value of the column can be edited when adding a new data record. Once the data record has been saved it can no longer be edited.
 - To withdraw permissions, disable the associated checkbox.
 - Use the **Delete** context menu item, to delete all permissions from a column.
6. Select the **Database > Save to database** and click **Save**.

Related topics

- [Editing table permissions](#) on page 55
- [Copying table permissions and column permissions](#) on page 57

Copying table permissions and column permissions

To transfer the permissions of a permissions group quickly from one table to another table, you can copy the table permissions and column permissions. Two methods are provided in the Permissions Editor to do this:

- **Copy** and **Insert:** This method copies permissions of the source table (source column) of a permissions group. The permissions are copied for the permissions group that you selected in the Permissions Editor toolbar in the **Permissions group** menu.
All copied permissions are inserted for the target table (target column). Already existing permissions for the target table (target column) remain the same.
- **Copy all permissions** and **Paste all permissions:** This method copies all source table (source column) permissions. The initial selection of the permissions group in the Permissions Editor makes no difference here. All permissions from all

permissions groups for the source table (source column) are applied.

All copied permissions are inserted for the target table (target column). Existing permissions for target table (target column) that do not exist for the source table (source column) are removed from the target table (target column).

To copy permissions of a permission group

1. In the Designer, select the **Permissions** category.
2. Start the Permissions Editor using the **Edit permissions** task.
3. In the Permissions Editor toolbar in the **Permissions group** menu, select the permissions group for which you want to grant the permissions.
4. To transfer the table permissions.
 - a. Select the table at the top of the Permissions Editor from which you want to transfer the permissions.
 - b. Use the **Copy** context menu item to copy the permissions to the clipboard.
 - c. Select the table at the top of the Permissions Editor from which you want to transfer the permissions.
 - d. Use the **Insert** context menu to insert the permissions.
 - e. If necessary, repeat step c) and d) for other tables.
5. To transfer the column permissions
 - a. Select the table at the top of the Permissions Editor and select the column from which you want to transfer permissions.
 - b. Use the **Copy** context menu to copy the permissions.
 - c. Select the table at the top of the Permissions Editor and select the column for which you want to transfer permissions.
 - d. Use the **Insert** context menu to insert the permissions.
 - e. If necessary, repeat step c) and d) for other columns.
6. Select the **Database > Save to database** and click **Save**.

Related topics

- [Editing table permissions](#) on page 55
- [Editing column permissions](#) on page 56

Simulating permissions for system users

By simulating the permissions in the Permissions Editor, you can see which permissions a system user has based on their permissions group. You can specify which permissions groups of a system user to include in the simulation. The result displayed shows which of the selected permissions groups has which table permissions and column permissions. Effective permissions for the system user are also displayed.

NOTE: Simulation mode remains active until you end it. In simulation mode, you can edit permissions group permissions and update simulation data.

To run a simulation:

1. In the Designer, select the **Permissions** category.
2. Start the Permissions Editor using the **Edit translation in database** task.
3. From the **Simulation > Start simulation** menu, start the simulation wizard.
4. On the start page of the wizard, click **Next**.
5. On the **Simulation base configuration** page, select the following data.
 - **User:** Select the system user whose permissions you want to simulate.
 - **Direct groups:** Use this button to select all permissions groups that are directly assigned to the system user.
 - **All groups:** Use this button to select all permissions groups that are directly assigned to the system user as well as all permissions groups that the system user inherits indirectly.
 - **Permissions groups:** Select individual permissions groups directly. Use **Ctrl + select** to select multiple permissions groups.
6. On the **Simulation configuration** page, specify the tables for which the permissions are simulated.
 - In the **Selected tables** pane, all tables of the One Identity Manager schema are selected. If necessary, limit the selection to individual tables. Click **None** to undo the selection. Use **Shift + select** to select individual tables.
 - Using the **Context table** menu, you can specify a table from which you can view the resulting implicit permissions for the foreign key columns display values.

Example:

For the Employee table, viewing permissions have been assigned to the UID_Org column. As a result, viewing permissions are implicitly assigned to columns of the Org table that are used as a display template, for example, Org.Ident_Org.

To simulate this example, select the **Employee table** under Context table and the **Org table** under Selected tables.

7. The processing progress of the simulation is displayed on the **Simulation** page. The simulation process can take some time.
8. To end the wizard, click **Finish** on the last page.

After you complete simulation wizard, the system user's effective table permissions and column permissions are displayed in the upper part of the Permissions Editor in the **Simulation** view.

9. To determine which table permission or column permission results from which of the system user's permissions groups, select the table or column in the upper part of the Permissions Editor.

The permissions and permissions groups are displayed in the **Permissions simulation** view in the lower part of the Permissions Editor.

10. To end the simulation mode, select the **Simulation > End simulation** menu.

The simulation data is deleted and the **Permissions simulation** view is closed.

Displaying permissions for objects

You can display object properties and permissions in One Identity Manager tools.

NOTE: The Manager must be running in expert mode to show object properties.

To view an object's permissions

1. Select the object and open the **Properties** context menu.
2. Select the **Permissions** tab.

On the **Permissions** tab, based on the permissions groups, you see what permissions apply to an object. The first entry shows the basic permissions for the table. The permissions for this particular object are displayed beneath that. The other entries show the column permissions.

TIP: Double-click the table entry, the object entry, or a column entry to display the permissions group from which the permissions were determined.

Table 25: Icon used for permissions

Icon	Meaning
✓	Permissions exist.
•	Permissions have been removed by the object layer.
☑	Permissions limited by conditions.

Displaying permissions for the current user

To get more information about the current user

- To display user information, double-click the  icon in the program status bar.

Table 26: Extra information about the current user

Property	Meaning
System users	Name of system user
Authenticated by	Name of the authentication module used for logging in.
Employee UID (UserUID)	Unique ID for the current user's employee if an employee related authentication module is used to log in.
SQL access level	Access level of the database server used to log in.
Read-only	The system user has only has read permissions. Modification to data are not possible.
Dynamic user	The current user uses a dynamic system user. Dynamic system users are applied when a role-based authentication module is used.
Administrative user	The current user uses an administrative system user.
Remarks	More details about the system user in use.
Permissions group	Permissions groups that are assigned to the system user. The permissions groups determine the user's user interface and object permissions.
Program functions	Program functions assigned to the system user The menu items and functions available depend on the program functions.

Assigning role-based permissions groups to an applications

If you assign a permissions group to an application, the permissions of the group apply only to this application. When a user logs on to the application, they receive the permissions of the permissions group in addition to their own permissions.

To assign a role-based permissions group to an application

1. In the Designer, select the **Permissions > Permissions groups > Role based permissions groups** category.
2. Select **View > Select table relations** and enable the DialogGroupInProductLimited table.
3. In the List Editor, select the permissions group.
4. Assign the application in the **Applications** edit view.
5. Select the **Database > Save to database** and click **Save**.

For detailed information about applications in One Identity Manager, see the *One Identity Manager Configuration Guide*.

Managing permissions to program features

Program functions are part of the permission model in One Identity Manager. They allow you to enable and disable features. Program functions are not assigned to single users but to permissions groups. The set of program functions defined for a user is determined by their permissions groups and the program functions contained in them.


One Identity Manager tools can only be started if the user has the relevant program function permissions. Furthermore, some functions in the One Identity Manager tools are available only if the program functions are assigned to the current user. This includes data export from the Manager, calling the SQL Editor in the Designer or showing DBQueue Processor information in all programs, as examples.

Detailed information about this topic

- [Displaying permissions for the current user on page 61](#)
- [Assigning program functions to permissions groups on page 64](#)
- [Permissions for running scripts on page 64](#)
- [Permissions for running methods on page 65](#)
- [Permissions for triggering processes on page 66](#)
- [Modifying permissions for running actions in the Launchpad on page 67](#)
- [Program functions for starting the One Identity Manager tools on page 133](#)

Displaying the current user's program functions

To identify the program functions available to the current user:

- To display user information, double-click the icon in the program status bar 
The **Program functions** tab shows the program functions that are available.

Assigning program functions to permissions groups

To assign a program function to permissions groups

1. In the Designer, select the **Permissions > Program functions** category.
2. Select the **View > Select table relations** menu item and enable the DialogGroupHasFeature table.
3. In the List Editor, select the program function.
4. Assign the permissions group in the **Permissions groups** edit view.
5. Select the **Database > Save to database** and click **Save**.

Related topics

- [Adding system users to permission groups](#) on page 50

Permissions for running scripts

The basic permissions for running scripts are granted to the logged in user through the program feature **Allow the starting of arbitrary scripts from the frontend** (Common_StartScripts).

If a script is assigned a program function (QBMScriptHasFeature table), users can only run this script if they have the necessary permissions groups. An error occurs if the user does not own this program function and tries to run it.

To control how a script is run using a program function

1. Create a new program function.
 - a. In the Designer, select the **Permissions > Program functions** category.
 - b. Select the **Object > New** menu item.
 - c. Enter the following information:
 - **Program function:** Name of the program function.
 - **Description:** Short description of the program function.
 - **Function group:** Property for grouping program functions.
2. Connect the program function with the scripts that the user are allowed to trigger.
 - a. In the Designer, select the **Permissions > Program functions** category.
 - b. Select the **View > Select table relations** menu item and enable the QBMScriptHasFeature table.

- c. In the List Editor, select the newly created program function.
 - d. In the **Scripts** edit view, assign the scripts.
3. Assign the required program functions to the custom permissions group whose systems users will run these scripts.
 - a. In the Designer, select the **Permissions > Program functions** category.
 - b. Select the **View > Select table relations** menu item and enable the DialogGroupHasFeature table.
 - c. In the List Editor, select your newly created program function.
 - d. In the List Editor, use **Ctrl+Selection** to select your newly created program function and the **Allow the starting of arbitrary scripts from the frontend** function (Common_StartScripts).
 - e. Assign the permissions group in the **Permissions groups** edit view.
4. Select the **Database > Save to database** and click **Save**.

Related topics

- [Editing permissions groups](#) on page 42

Permissions for running methods

If a task definition is assigned a program function (QBMethodHasFeature table) users can only run this task if they have the necessary permissions groups. An error occurs if the user does not own this program function and tries to run it.

To make a task definition available to users using a program function

1. Create a new program function.
 - a. In the Designer, select the **Permissions > Program functions** category.
 - b. Select the **Object > New** menu item.
 - c. Enter the following information:
 - **Program function:** Name of the program function.
 - **Description:** Short description of the program function.
 - **Function group:** Property for grouping program functions.
2. Connect the program function with the task definition events that the user will trigger.
 - a. In the Designer, select the **Permissions > Program functions** category.
 - b. Select the **View > Select table relations** menu item and enable the QBMethodHasFeature table.

- c. In the List Editor, select the newly created program function.
 - d. In the **Tasks** edit view, assign the task definitions.
3. Assign the program functions to the custom permissions group whose systems users will run these scripts.
 - a. In the Designer, select the **Permissions > Program functions** category.
 - b. Select the **View > Select table relations** menu item and enable the DialogGroupHasFeature table.
 - c. In the List Editor, select your newly created program function.
 - d. Assign the permissions group in the **Permissions groups** edit view.
4. Select the **Database > Save to database** and click **Save**.

Related topics

- [Editing permissions groups](#) on page 42

Permissions for triggering processes

The basic permissions for triggering processes are granted to the logged in user by the **Allow to trigger any events from the frontend** program feature (Common_TriggerEvents).

In One Identity Manager, triggering of events on stored processes is linked to the permissions concept. Users can only trigger events on objects like this if they own edit permissions for them. This can lead to table users who only have viewing permissions not being able to trigger additional events for processes.

In this case, it is possible to connect the object events (QBMEvent table) with a program function (QBFeature table). An event (JobEventGen table), which is defined for a process, is linked with an object event (JobEventGen.UID_QBMEvent column). The object events are linked to a program function (QBEventHasFeature table). Users with this program function can trigger the object event and therefore the process too independent of their permissions.

To control triggering a process through a program function

1. Create a new program function.
 - a. In the Designer, select the **Permissions > Program functions** category.
 - b. Select the **Object > New** menu item.
 - c. Enter the following information:
 - **Program function:** Name of the program function.
 - **Description:** Short description of the program function.
 - **Function group:** Property for grouping program functions.

2. Connect the program function with object events that the user will trigger.
 - a. In the Designer, select the **Permissions > Program functions** category.
 - b. Select the **View > Select table relations** menu item and enable the QBMEventHasFeature table.
 - c. In the List Editor, select the newly created program function.
 - d. In the **Object events** edit view, assign the object events.
3. Assign the required program functions to the custom permissions group whose systems users will trigger these events.
 - a. In the Designer, select the **Permissions > Program functions** category.
 - b. Select the **View > Select table relations** menu item and enable the DialogGroupHasFeature table.
 - c. In List Editor, use **Ctrl+Selection** to select your newly created program function and the function **Allow to trigger any events from the frontend** (Common_TriggerEvents).
 - d. Assign the permissions group in the **Permissions groups** edit view.
4. Select the **Database > Save to database** and click **Save**.

Related topics

- [Editing permissions groups](#) on page 42

Modifying permissions for running actions in the Launchpad

One Identity Manager supplies a number of Launchpad actions that you can use to start applications by using the Launchpad. You can also start your own applications over the Launchpad.

If some actions in the Launchpad should not be made available to all users, you can manage the permissions by assigning Launchpad actions to program functions (QBMLaunchActionHasFeature table). Only tasks containing actions that the user's program function permissions permit him to run are shown in the Launchpad.

To assign a program function to Launchpad actions

1. In the Designer, select the **Permissions > Program functions** category.
2. Select the **View > Select table relations** menu item and enable the QBMLaunchActionHasFeature table.
3. In the List Editor, select the program function.
4. In the **Launchpad action** edit view, assign the actions.
5. Select the **Database > Save to database** and click **Save**.

One Identity Manager authentication modules

One Identity Manager uses different authentication modules for logging in to administration tools. Authentication modules identify the system users to be used and load the user interface and database resource editing permissions depending on their permission group memberships.

- The permissions assigned to the system user are found from the permissions groups for logging into One Identity Manager tools with an authentication module that expects a defined system user.
- Dynamic system users are used for logging into One Identity Manager tools with role-based authentication modules. First, the employee memberships in the One Identity Manager application roles are determined during login. Assignments of permissions groups to One Identity Manager application roles are used to determine which permissions groups apply to the employee. A dynamic system user is determined from these permissions groups that will be used for the employee's login.

Before you can use an authentication module for logging on, the following prerequisites must be fulfilled:

1. The authentication module must be enabled.
2. The authentication module must be assigned to the application.
3. The assignment of the authentication module to the application must be enabled.

This allows you to log in to the assigned application using this authentication module. Ensure that users found through the authentication module also have the required program function to use the program.

NOTE: After the initial schema installation, only the **System user** and **Component authenticator** authentication modules and the role-based authentication modules are enabled in One Identity Manager.

Use non role-based authentication modules to log in to the Designer. Role-based authentication modules for logging in to the Designer are not supported.

NOTE: Authentication modules are defined in the One Identity Manager modules and are not available until the modules are installed.

Related topics

- [Enabling authentication modules on page 97](#)
- [Assigning authentication modules to applications on page 97](#)
- [Disabling or enabling authentication modules for applications on page 98](#)

System users

NOTE: This authentication module is available if the Configuration Module is installed.

Credentials	The system user's identifier and password.
Prerequisites	<ul style="list-style-type: none">• The system user with permissions exists in the One Identity Manager database.
Set as default	Yes
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	No
Remarks	<p>The user interface and the permissions are loaded through the system user.</p> <p>Data modifications are attributed to the system user.</p>

IMPORTANT: The **viadmin** system user is available by default. The system user has the predefined user interface and access permissions to database resources. You must not use or change the user interface and the permissions structure of the system user in live systems because this system user is overwritten with each schema update as it is from a system user template.

TIP: Create your own system user with the appropriate permissions. This can be done on initial installation of the One Identity Manager database. This system user can compile an initial One Identity Manager database and can be used to log into the administration tools for the first time.

Generic single sign-on (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials	The authentication module uses the login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none"> • The employee exists in the One Identity Manager database. • The employee is assigned at least one application role. • The user account exists in the One Identity Manager database and the employee is entered in the user account's main data.
Set as default	No
Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>One Identity Manager searches for the user account according to the configuration and finds the employee assigned to the user account.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none"> • If this configuration parameter is set, the employee's main identity is used for authentication. • If this configuration parameter is set, the employee's subidentity is used for authentication. <p>A dynamic system user is determined from the employee's application roles. The user interface and the permissions are loaded through this system user.</p> <p>Changes to the data are assigned to the logged in employee.</p>

Modify the following configuration parameters in the Designer to implement the authentication module.

Table 27: Configuration parameters for the authentication module

Configuration parameter	Meaning
QER Person GenericAuthenticator	Specifies whether authentication through single sign-on is supported.
QER Person GenericAuthenticator SearchTable	Table in the One Identity Manager schema which stores the user information. The table must contain a foreign key with the name UID_Person (or CCC_UID_Person) that references the Person table. Example: ADSAccount
QER Person GenericAuthenticator SearchTableColumn	Column from the One Identity Manager table (SearchTable)

Configuration parameter	Meaning
icAuthenticator SearchColumn	that is used to search for user name of the current user. Example: CN
QER Person GenericAuthenticator EnabledBy	Pipe () delimited list of Boolean columns from the One Identity Manager table (SearchTable) enabled by the user account for the login.
QER Person GenericAuthenticator DisabledBy	Pipe () delimited list of Boolean columns from the One Identity Manager table (SearchTable) disabled by the user account for the login. Example: AccountDisabled

Employee

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials	Employee's central user account and password.
Prerequisites	<ul style="list-style-type: none"> The system user with permissions exists in the One Identity Manager database. The employee exists in the One Identity Manager database. The central user account is entered in the employee's main data. The system user is entered in the employee's main data. The system user password is entered in the employee's main data.
Set as default	Yes
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none"> If this configuration parameter is set, the employee's main identity is used for authentication. If this configuration parameter is set, the employee's subidentity is used for authentication.

The user interface and permissions are loaded through the system user that is directly assigned to the logged in employee.

Changes to the data are assigned to the logged in employee.

Employee (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials	Employee's central user account and password.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• The central user account is entered in the employee's main data.• The system user password is entered in the employee's main data.• The employee is assigned at least one application role.
Set as default	Yes
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none">• If this configuration parameter is set, the employee's main identity is used for authentication.• If this configuration parameter is set, the employee's subidentity is used for authentication. <p>A dynamic system user is determined from the employee's application roles. The user interface and the permissions are loaded through this system user.</p> <p>Changes to the data are assigned to the logged in employee.</p>

Employee (dynamic)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials	Employee's central user account and password.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• The central user account is entered in the employee's main data.• The system user password is entered in the employee's main data.• The configuration data for dynamically determining the system user is defined in the application. Thus, an employee can, for example, be assigned a system user dynamically depending on their department membership.
Set as default	Yes
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none">• If this configuration parameter is set, the employee's main identity is used for authentication.• If this configuration parameter is set, the employee's subidentity is used for authentication. <p>The application configuration data is used to determine a system user, which is automatically assigned to the employee. The user interface and permissions are loaded through the system user that is dynamically assigned to the logged in employee.</p> <p>Changes to the data are assigned to the logged in employee.</p>

Related topics

- [Configuration data for system user dynamic authentication](#) on page 104

User account

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials	The authentication module uses the Active Directory login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none">• The system user with permissions exists in the One Identity Manager database.• The employee exists in the One Identity Manager database.• Permitted logins are entered in the employee's main data. The logins are expected in the form: domain\user.• The system user is entered in the employee's main data.
Set as default	No
Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>All employee logins saved in the One Identity Manager database are found. The employee whose login data matches that of the current user is used for logging in.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none">• If this configuration parameter is set, the employee's main identity is used for authentication.• If this configuration parameter is set, the employee's subidentity is used for authentication. <p>The user interface and permissions are loaded through the system user that is directly assigned to the employee found.</p> <p>Data modifications are attributed to the current user account.</p>

User account (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

Credentials	The authentication module uses the Active Directory login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none"> • The employee exists in the One Identity Manager database. • Permitted logins are entered in the employee's main data. The logins are expected in the form: domain\user. • The employee is assigned at least one application role.
Set as default	No
Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>All employee logins saved in the One Identity Manager database are found. The employee whose login data matches that of the current user is used for logging in.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none"> • If this configuration parameter is set, the employee's main identity is used for authentication. • If this configuration parameter is set, the employee's subidentity is used for authentication. <p>A dynamic system user is determined from the employee's application roles. The user interface and the permissions are loaded through this system user.</p> <p>Data modifications are attributed to the current user account.</p>

Account based system user

NOTE: This authentication module is available if the Configuration Module is installed.

Credentials	The authentication module uses the Active Directory login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none"> • The system user with permissions exists in the One Identity Manager database. • Permitted logins are entered in the system user's main data. The logins are expected in the form: domain\user.

Set as default	No
Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	No
Remarks	<p>All system user logins saved in the One Identity Manager database are found. The system user whose login data matches that of the current user is used for logging in.</p> <p>The user interface and the permissions are loaded through the system user.</p> <p>Data modifications are attributed to the current user account.</p>

Active Directory user account

NOTE: This authentication module is available if the Active Directory Module is installed.

Credentials	The authentication module uses the Active Directory login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none"> • The system user with permissions exists in the One Identity Manager database. • The employee exists in the One Identity Manager database. • The system user is entered in the employee's main data. • The Active Directory user account exists in the One Identity Manager database and the employee is entered in the user account's main data.
Set as default	Yes
Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>The appropriate user account is found in the One Identity Manager database through the user's SID and the domain given at login. One Identity Manager determines which employee is assigned to the user account.</p> <p>If an employee has more than one identity, the QER Person </p>

MasterIdentity | UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If this configuration parameter is set, the employee's subidentity is used for authentication.

The user interface and permissions are loaded through the system user that is directly assigned to the employee found. If a system user is not assigned to the employee, the system user from the **SysConfig | Logon | DefaultUser** configuration parameter is used.

Data modifications are attributed to the current user account.

NOTE: If the **Connect automatically** option is set, authentication is no longer necessary for subsequent logins.

Active Directory user account (role-based)

NOTE: This authentication module is available if the Active Directory Module is installed.

Credentials	The authentication module uses the Active Directory login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• The employee is assigned at least one application role.• The Active Directory user account exists in the One Identity Manager database and the employee is entered in the user account's main data.
Set as default	Yes
Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>The appropriate user account is found in the One Identity Manager database through the user's SID and the domain given at login. One Identity Manager determines which employee is assigned to the user account.</p> <p>If an employee has more than one identity, the QER Person </p>

MasterIdentity | UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If this configuration parameter is set, the employee's subidentity is used for authentication.

A dynamic system user is determined from the employee's application roles. The user interface and the permissions are loaded through this system user.

Data modifications are attributed to the current user account.

NOTE: If the **Connect automatically** option is set, authentication is no longer necessary for subsequent logins.

Active Directory user account (manual input)

NOTE: This authentication module is available if the Active Directory Module is installed.

Credentials	Login name and password for registering with Active Directory. You do not have to enter the domain.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• The Active Directory user account exists in the One Identity Manager database and the employee is entered in the user account's main data.• Domains permitted for login are entered in the TargetSystem ADS AuthenticationDomains configuration parameter.• The configuration data for dynamically determining the system user is defined in the application. Thus, an employee can, for example, be assigned a system user dynamically depending on their department membership.
Set as default	No
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	The user's identity is determined from a predefined list of permitted

Active Directory domains. The corresponding user account and employee are determined in the One Identity Manager database, which the user account is assigned to.

If an employee has more than one identity, the **QER | Person | MasterIdentity | UseMasterForAuthentication** configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If this configuration parameter is set, the employee's subidentity is used for authentication.

The application configuration data is used to determine a system user, which is automatically assigned to the employee. The user interface and permissions are loaded through the system user that is dynamically assigned to the logged in employee.

Data modifications are attributed to the current user account.

Active Directory user account (manual input/role-based)

NOTE: This authentication module is available if the Active Directory Module is installed.

Credentials	Login name and password for registering with Active Directory. You do not have to enter the domain.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• The employee is assigned at least one application role.• The Active Directory user account exists in the One Identity Manager database and the employee is entered in the user account's main data.• Domains permitted for login are entered in the TargetSystem ADS AuthenticationDomains configuration parameter.
Set as default	Yes
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	The user's identity is determined from a predefined list of permitted

Active Directory domains. The corresponding user account and employee are determined in the One Identity Manager database, which the user account is assigned to.

If an employee has more than one identity, the **QER | Person | MasterIdentity | UseMasterForAuthentication** configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If this configuration parameter is set, the employee's subidentity is used for authentication.

A dynamic system user is determined from the employee's application roles. The user interface and the permissions are loaded through this system user.

Data modifications are attributed to the current user account.

Active Directory user account (dynamic)

| NOTE: This authentication module is available if the Active Directory Module is installed.

Credentials	The authentication module uses the Active Directory login data of the user currently logged in on the workstation.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• The Active Directory user account exists in the One Identity Manager database and the employee is entered in the user account's main data.• The configuration data for dynamically determining the system user is defined in the application. Thus, an employee can, for example, be assigned a system user dynamically depending on their department membership.
Set as default	No
Single sign-on	Yes
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	The appropriate user account is found in the One Identity Manager database through the user's SID and the domain given at login. One Identity Manager determines which employee is assigned to the user account.

If an employee has more than one identity, the **QER | Person | MasterIdentity | UseMasterForAuthentication** configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If this configuration parameter is set, the employee's subidentity is used for authentication.

The application configuration data is used to determine a system user, which is automatically assigned to the employee. The user interface and permissions are loaded through the system user that is dynamically assigned to the logged in employee.

Data modifications are attributed to the current user account.

NOTE: If the **Connect automatically** option is set, authentication is no longer necessary for subsequent logins.

Related topics

- [Configuration data for system user dynamic authentication](#) on page 104

LDAP user account (role-based)

NOTE: This authentication module is available if the LDAP Module is installed.

Credentials	Login name, identifier, distinguished name or user ID of an LDAP user account. LDAP user account's password.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• The employee is assigned at least one application role.• The LDAP user account exists in the One Identity Manager database and the employee is entered in the user account's main data.• The configuration data for dynamically determining the system user is defined in the application. Thus, an employee can, for example, be assigned a system user dynamically depending on their department membership.
Set as default	No
Single sign-on	No
Front-end login allowed	Yes

Web Portal login allowed	Yes
Remarks	<p>If you log in using a login name, identifier, or user ID, the corresponding user account is determined in the One Identity Manager database through the domain. Domains permitted for login are entered in the TargetSystem LDP Authentication RootDN configuration parameter. If log in uses a distinguished name, the LDAP user account is determined that uses this distinguished name. One Identity Manager determines which employee is assigned to the LDAP user account.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none"> • If this configuration parameter is set, the employee's main identity is used for authentication. • If this configuration parameter is set, the employee's subidentity is used for authentication. <p>A dynamic system user is determined from the employee's application roles. The user interface and the permissions are loaded through this system user.</p> <p>Data modifications are attributed to the current user account.</p>

In the Designer, modify the following configuration parameters to implement the authentication module.

Table 28: Configuration parameters for the authentication module

Configuration parameter	Meaning
TargetSystem LDAP Authentication	Allows configuration of the LDAP authentication module.
TargetSystem LDAP Authentication Authentication	<p>Authentication mechanism. Permitted values are Secure, Encryption, SecureSocketsLayer, ReadonlyServer, Anonymous, FastBind, Signing, Sealing, Delegation, and ServerBind. The value can be combined with commas (,). For more information about authentication types, see the MSDN Library.</p> <p>The default is ServerBind.</p>
TargetSystem LDAP Authentication Port	LDAP server's port. The default is port 389 .
TargetSystem LDAP Authentication RootDN	Pipe () delimited list of root domains to be used to find the user account for authentication.

Configuration parameter	Meaning
	Syntax: DC=<MyDomain> DC=<MyOtherDomain> Example: DC=Root1,DC=com DC=Root2,DC=de
TargetSystem LDAP Authentication Server	Name of the LDAP server.

LDAP user account (dynamic)

NOTE: This authentication module is available if the LDAP Module is installed.

Credentials	Login name, identifier, distinguished name or user ID of an LDAP user account. LDAP user account's password.
Prerequisites	<ul style="list-style-type: none"> The employee exists in the One Identity Manager database. The LDAP user account exists in the One Identity Manager database and the employee is entered in the user account's main data. The configuration data for dynamically determining the system user is defined in the application. Thus, an employee can, for example, be assigned a system user dynamically depending on their department membership.
Set as default	No
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	If you log in using a login name, identifier, or user ID, the corresponding user account is determined in the One Identity Manager database through the domain. Domains permitted for login are entered in the TargetSystem LDP Authentication RootDN configuration parameter. If log in uses a distinguished name, the LDAP user account is determined that uses this distinguished name. One Identity Manager determines which employee is assigned to the LDAP user account. If an employee has more than one identity, the QER Person

MasterIdentity | UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If this configuration parameter is set, the employee's subidentity is used for authentication.

The application configuration data is used to determine a system user, which is automatically assigned to the employee. The user interface and permissions are loaded through the system user that is dynamically assigned to the logged in employee.

Data modifications are attributed to the current user account.

In the Designer, modify the following configuration parameters to implement the authentication module.

Table 29: Configuration parameters for the authentication module

Configuration parameter	Meaning
TargetSystem LDAP Authentication	Allows configuration of the LDAP authentication module.
TargetSystem LDAP Authentication Authentication	Authentication mechanism. Permitted values are Secure , Encryption , SecureSocketsLayer , ReadonlyServer , Anonymous , FastBind , Signing , Sealing , Delegation , and ServerBind . The value can be combined with commas (,). For more information about authentication types, see the MSDN Library . The default is ServerBind .
TargetSystem LDAP Authentication Port	LDAP server's port. The default is port 389 .
TargetSystem LDAP Authentication RootDN	Pipe () delimited list of root domains to be used to find the user account for authentication. Syntax: DC=<MyDomain> DC=<MyOtherDomain> Example: DC=Root1,DC=com DC=Root2,DC=de
TargetSystem LDAP Authentication Server	Name of the LDAP server.

Related topics

- [Configuration data for system user dynamic authentication](#) on page 104

HTTP header

| NOTE: This authentication module is available if the Configuration Module is installed.

The authentication module supports authentication by web single sign-on solutions that work with a proxy-based architecture.

Credentials	Employee's central user account or personnel number.
Prerequisites	<ul style="list-style-type: none">• The system user with permissions exists in the One Identity Manager database.• The employee exists in the One Identity Manager database.• The central user account or personnel number is entered in the employee's main data.• The system user is entered in the employee's main data.
Set as default	No
Single sign-on	Yes
Front-end login allowed	No
Web Portal login allowed	Yes
Remarks	<p>You must pass the user (in the form: UserName =<user name of authenticated user>) in the HTTP header. The employee is found in the One Identity Manager database whose central user account or personnel number matches the user name passed down.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none">• If this configuration parameter is set, the employee's main identity is used for authentication.• If this configuration parameter is set, the employee's subidentity is used for authentication. <p>The user interface and permissions are loaded through the system user that is directly assigned to the logged in employee. If a system user is not assigned to the employee, the system user from the SysConfig Logon DefaultUser configuration parameter is used.</p> <p>Changes to the data are assigned to the logged in employee.</p>

HTTP header (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

The authentication module supports authentication by web single sign-on solutions that work with a proxy-based architecture.

Credentials	Employee's central user account or personnel number.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• The central user account or personnel number is entered in the employee's main data.• The employee is assigned at least one application role.
Set as default	Yes
Single sign-on	Yes
Front-end login allowed	No
Web Portal login allowed	Yes
Remarks	<p>You must pass the user (in the form: UserName =<user name of authenticated user>) in the HTTP header. The employee is found in the One Identity Manager database whose central user account or personnel number matches the user name passed down.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none">• If this configuration parameter is set, the employee's main identity is used for authentication.• If this configuration parameter is set, the employee's subidentity is used for authentication. <p>A dynamic system user is determined from the employee's application roles. The user interface and the permissions are loaded through this system user.</p> <p>Changes to the data are assigned to the logged in employee.</p>

OAuth 2.0/OpenID Connect

NOTE: This authentication module is available if the Identity Management Base Module is installed.

The authorization module supports the authorization code for OAuth 2.0 and OpenID Connect. For more information about the authorization code flow, see, for example, the [OAuth Specification](#) or the [OpenID Connect Specification](#).

This authentication module uses a Secure Token Service for logging in. This login procedure can be used with every Secure Token Service that can return an OAuth 2.0 token.

Credentials	Dependent on the authentication method of the secure token service.
Prerequisites	<ul style="list-style-type: none">• The system user with permissions exists in the One Identity Manager database.• The employee exists in the One Identity Manager database.• The system user is entered in the employee's main data.• The user account exists in the One Identity Manager database and the employee is entered in the user account's main data.
Set as default	No
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>One Identity Manager determines which employee is assigned to the user account.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none">• If this configuration parameter is set, the employee's main identity is used for authentication.• If this configuration parameter is set, the employee's subidentity is used for authentication. <p>The user interface and permissions are loaded through the system user that is directly assigned to the employee found.</p> <p>Data modifications are attributed to the current user account. To do this, the claim type whose value is used for labeling data changes must be declared.</p>

NOTE: If the authentication module cannot find a matching user for the claim value, it searches for the claim value in permitted system users' credentials (DialogUser.AuthenticatorLogons). If an entry is found there, then that system user is logged in. To allocate the data changes, the values are used from the respective claims. If a matching user is found, the fallback cannot be used anymore.

Related topics

- [OAuth 2.0 / OpenID Connect configuration](#) on page 109
- [Expiry of the OAuth 2.0/OpenID Connect authentication](#) on page 109

OAuth 2.0/OpenID Connect (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

The authorization module supports the authorization code for OAuth 2.0 and OpenID Connect. For more information about the authorization code flow, see, for example, the [OAuth Specification](#) or the [OpenID Connect Specification](#).

This authentication module uses a Secure Token Service for logging in. This login procedure can be used with every Secure Token Service that can return an OAuth 2.0 token.

Credentials	Dependent on the authentication method of the secure token service.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• The employee is assigned at least one application role.• The user account exists in the One Identity Manager database and the employee is entered in the user account's main data.
Set as default	No
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>One Identity Manager determines which employee is assigned to the user account.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p>

- If this configuration parameter is set, the employee's main identity is used for authentication.
- If this configuration parameter is set, the employee's subidentity is used for authentication.

A dynamic system user is determined from the employee's application roles. The user interface and the permissions are loaded through this system user.

Data modifications are attributed to the current user account. To do this, the claim type whose value is used for labeling data changes must be declared.

NOTE: If the authentication module cannot find a matching user for the claim value, it searches for the claim value in permitted system users' credentials (DialogUser.AuthenticatorLogons). If an entry is found there, then that system user is logged in. To allocate the data changes, the values are used from the respective claims. If a matching user is found, the fallback cannot be used anymore.

Related topics

- [OAuth 2.0 / OpenID Connect configuration](#) on page 109
- [Expiry of the OAuth 2.0/OpenID Connect authentication](#) on page 109

Synchronization authentication module

NOTE: This authentication module is available if the Target System Synchronization Module is installed.

This authentication module integrates the default method for Synchronization Editor login.

Credentials	Login uses the sa system user.
Prerequisites	
Set as default	Yes
Single sign-on	No
Front-end login allowed	No
Web Portal login allowed	No
Remarks	You must not change the system user sa . The system user is overwritten with each schema update.

Web agent authentication module

| NOTE: This authentication module is available if the Configuration Module is installed.

The authentication module integrates the default method for Web Designer login, to access the database before the first user login.

Credentials	Login uses the sa system user.
Prerequisites	
Set as default	Yes
Single sign-on	No
Front-end login allowed	No
Web Portal login allowed	No
Remarks	You must not change the system user sa . The system user is overwritten with each schema update.

Component authentication module

| NOTE: This authentication module is available if the Configuration Module is installed.

This authentication module integrates the default method for registering process components.

Credentials	Login uses the sa system user.
Prerequisites	
Set as default	Yes
Single sign-on	No
Front-end login allowed	No
Web Portal login allowed	No
Remarks	You must not change the system user sa . The system user is overwritten with each schema update.

Crawler

NOTE: This authentication module is available if the Configuration Module is installed.

The authentication module is used by the application server to compile search indexes for full text search over the database.

Credentials	Login uses the sa system user.
Prerequisites	
Set as default	Yes
Single sign-on	No
Front-end login allowed	No
Web Portal login allowed	No
Remarks	You must not change the system user sa . The system user is overwritten with each schema update.

Password reset

NOTE: This authentication module is available if the Identity Management Base Module is installed.

The authentication module is used for login to Password Reset Portal. The authentication module checks the passcode or the employee's answers to the password questions. In the case of login with an passcode, this information is deleted after a successful login.

Credentials	Central user account and passcode. - OR - Central user account and answers to the password questions. - OR - Target system user account and passcode. - OR - Target system user account and answers to password questions.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• Using the central user account: The central user account is entered in the employee's main data.

- Using the target system user account: The user account exists in the One Identity Manager database and the employee is entered in the main data of the employee's user account.
- The employee is not deactivated or has the certification status **New**.
- The employee has an passcode or the questions and answers for the password prompt have been specified.

Set as default No

Single sign-on No

Front-end
login allowed No

Web Portal
login allowed No

Remarks The application token for Password Reset Portal must be specified. You set the application token when installing Password Reset Portal. The application token is saved as a hash value in the database in the **QER | Person | PasswordResetAuthenticator | ApplicationToken** parameter and stored encrypted in the web.config file. For detailed information about configuring the Password Reset Portal, see the *One Identity Manager Web Application Configuration Guide*.

In the Designer, modify the following configuration parameters so that target system accounts can be used for logging in. If the configuration parameters are not set, the employee's central user account is used.

Table 30: Configuration parameters for the authentication module

Configuration parameter	Meaning
QER Person PasswordResetAuthenticator SearchTable	Table in the One Identity Manager schema which stores the user information. The table must contain a foreign key with the name UID_Person (or CCC_UID_Person) that references the Person table. Example: ADSAccount
QER Person PasswordResetAuthenticator SearchColumn	Column from the One Identity Manager table (SearchTable) that is used to search for user name of the current user. Example: CN
QER Person PasswordResetAuthenticator EnabledBy	Pipe () delimited list of Boolean columns from the One Identity Manager table (SearchTable) enabled by the user account for the login.
QER Person PasswordResetAuthenticator DisabledBy	Pipe () delimited list of Boolean columns from the One Identity Manager table (SearchTable) disabled by the user account for the login. Example: AccountDisabled

Password reset (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

The authentication module is used for login to Password Reset Portal. The authentication module checks the passcode or the employee's answers to the password questions. In the case of login with an passcode, this information is deleted after a successful login.

Credentials	Central user account and passcode. - OR - Central user account and answers to the password questions. - OR - Target system user account and passcode. - OR - Target system user account and answers to password questions.
Prerequisites	<ul style="list-style-type: none">• The employee exists in the One Identity Manager database.• Using the central user account: The central user account is entered in the employee's main data.• Using the target system user account: The user account exists in the One Identity Manager database and the employee is entered in the main data of the employee's user account.• The employee is not deactivated or has the certification status New.• The employee has an passcode or the questions and answers for the password prompt have been specified.• The employee is assigned at least one application role.
Set as default	Yes
Single sign-on	No
Front-end login allowed	No
Web Portal login allowed	No
Remarks	The application token for Password Reset Portal must be specified. You set the application token when installing Password Reset Portal. The application token is saved as a hash value in the database in the QER Person PasswordResetAuthenticator ApplicationToken parameter and stored encrypted in the web.config file. For detailed information about configuring the Password Reset Portal, see the <i>One Identity Manager Web Application Configuration Guide</i> .

A dynamic system user is determined from the employee's application roles. The user interface and the permissions are loaded through this system user.

In the Designer, modify the following configuration parameters so that target system accounts can be used for logging in. If the configuration parameters are not set, the employee's central user account is used.

Table 31: Configuration parameters for the authentication module

Configuration parameter	Meaning
QER Person PasswordResetAuthenticator SearchTable	Table in the One Identity Manager schema which stores the user information. The table must contain a foreign key with the name UID_Person (or CCC_UID_Person) that references the Person table. Example: ADSAccount
QER Person PasswordResetAuthenticator SearchColumn	Column from the One Identity Manager table (SearchTable) that is used to search for user name of the current user. Example: CN
QER Person PasswordResetAuthenticator EnabledBy	Pipe () delimited list of Boolean columns from the One Identity Manager table (SearchTable) enabled by the user account for the login.
QER Person PasswordResetAuthenticator DisabledBy	Pipe () delimited list of Boolean columns from the One Identity Manager table (SearchTable) disabled by the user account for the login. Example: AccountDisabled

Decentralized identity

NOTE: This authentication module is available if the Identity Management Base Module is installed.

The authentication module can be used to log in using a decentralized identity.

Credentials	The employee's email address and decentralized identity.
Prerequisites	<ul style="list-style-type: none">• The system user with permissions exists in the One Identity Manager database.• The employee exists in the One Identity Manager database.• The decentralized identity is entered in the employee main data.

	<ul style="list-style-type: none"> • The default email address or the contact email address is in the employee's main data. • The system user is entered in the employee's main data.
Set as default	No
Single sign-on	No
Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>To identify the employee, the email address provided during login is verified against the default email address and the contact email address.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none"> • If this configuration parameter is set, the employee's main identity is used for authentication. • If this configuration parameter is set, the employee's subidentity is used for authentication. <p>The user interface and permissions are loaded through the system user that is directly assigned to the logged in employee.</p> <p>Changes to the data are assigned to the logged in employee.</p>

Decentralized Identity (role-based)

NOTE: This authentication module is available if the Identity Management Base Module is installed.

The authentication module can be used to log in using a decentralized identity.

Credentials	The employee's email address and decentralized identity.
Prerequisites	<ul style="list-style-type: none"> • The employee exists in the One Identity Manager database. • The decentralized identity is entered in the employee main data. • The default email address or the contact email address is in the employee's main data. • The employee is assigned at least one application role.
Set as default	No
Single sign-on	No

Front-end login allowed	Yes
Web Portal login allowed	Yes
Remarks	<p>To identify the employee, the email address provided during login is verified against the default email address and the contact email address.</p> <p>If an employee has more than one identity, the QER Person MasterIdentity UseMasterForAuthentication configuration parameter controls which employee identity is used for authentication.</p> <ul style="list-style-type: none"> • If this configuration parameter is set, the employee's main identity is used for authentication. • If this configuration parameter is set, the employee's subidentity is used for authentication. <p>A dynamic system user is determined from the employee's application roles. The user interface and the permissions are loaded through this system user.</p> <p>Changes to the data are assigned to the logged in employee.</p>

Editing authentication modules

Before you can use an authentication module for logging on, the following prerequisites must be fulfilled:

1. The authentication module must be enabled.
2. The authentication module must be assigned to the application.
3. The assignment of the authentication module to the application must be enabled.

This allows you to log in to the assigned application using this authentication module. Ensure that users found through the authentication module also have the required program function to use the program.

Detailed information about this topic

- [Enabling authentication modules](#) on page 97
- [Assigning authentication modules to applications](#) on page 97
- [Disabling or enabling authentication modules for applications](#) on page 98
- [Authentication module properties](#) on page 99
- [Initial data for authentication modules](#) on page 99
- [Configuration data for system user dynamic authentication](#) on page 104
- [One Identity Manager authentication modules](#) on page 68

- [Managing permissions to program features](#) on page 63
- [Program functions for starting the One Identity Manager tools](#) on page 133

Enabling authentication modules

NOTE: After the initial schema installation, only the **System user** and **Component authenticator** authentication modules and the role-based authentication modules are enabled in One Identity Manager.

To use an authentication module for logging in, you must enable the authentication module.

To enable an authentication module

1. In the Designer, select the **Base data > Security settings > Authentication modules** category.
2. In the List Editor, select the authentication module.
3. In the **Properties** view, set the **Activated** property to **True**.
4. Select the **Database > Save to database** and click **Save**.

Related topics

- [Disabling or enabling authentication modules for applications](#) on page 98
- [Assigning authentication modules to applications](#) on page 97

Assigning authentication modules to applications

NOTE: Use non role-based authentication modules to log in to the Designer. Role-based authentication modules for logging in to the Designer are not supported.

If create custom authentication modules, assign them to the existing programs. In general, you do not need to change assignments of predefined authentication modules.

To assign an authentication module to an application

1. In the Designer, select the **Base data > Security settings > Authentication modules** category.
2. Select the **View > Select table relations** menu item and enable the `DialogProductHasAuthentifier` table.
3. In List Editor, select the authentication module.
4. Assign the application in the **Applications** edit view.
5. Select the **Database > Save to database** and click **Save**.

Related topics

- [Disabling or enabling authentication modules for applications](#) on page 98
- [Enabling authentication modules](#) on page 97

Disabling or enabling authentication modules for applications

NOTE: Use non role-based authentication modules to log in to the Designer. Role-based authentication modules for logging in to the Designer are not supported.

To use an authentication module for login, assignment of the authentication module to the application must be enabled.

To enable an authentication module for an application

1. In the Designer, select the **Base data > Security settings > Authentication modules** category.
2. Select the **View > Select table relations** menu item and enable the DialogProductHasAuthentifier table.
3. In List Editor, select the authentication module.
4. In the **Application** edit view, select the assigned application.
5. Disable the **Disable** option.
6. Select the **Database > Save to database** and click **Save**.

To disable an authentication module for an application

1. In the Designer, select the **Base data > Security settings > Authentication modules** category.
2. Select the **View > Select table relations** menu item and enable the DialogProductHasAuthentifier table.
3. In List Editor, select the authentication module.
4. In the **Application** edit view, select the assigned application.
5. Enable the **Disable** option.
6. Select the **Database > Save to database** and click **Save**.

Related topics

- [Assigning authentication modules to applications](#) on page 97
- [Enabling authentication modules](#) on page 97

Authentication module properties

Table 32: Authentication module properties

Property	Meaning
Enabled	Specifies whether the authentication module can be used.
Display name	Display name for displaying the authentication module in the connection dialog of the administration tools.
Authentication module	Internal name of the authentication module.
Authentication type	Authentication module type. You can choose from Dynamic and Role based .
Processing status	The processing status is used for creating custom configuration packages.
Initial data	Initial data for logging in with this authentication module.
Class	Authentication module class.
Assembly name	Name of the assembly file.
Sort order	Specify the order in which the modules are displayed in the login window.
Single sign-on	Specifies whether the authentication module may be authenticated without a password.
Select in front-end	Specifies whether the authentication module can be selected in the login window.

Related topics

- [Enabling authentication modules](#) on page 97
- [Assigning authentication modules to applications](#) on page 97
- [Disabling or enabling authentication modules for applications](#) on page 98
- [Initial data for authentication modules](#) on page 99

Initial data for authentication modules

The initial data is one part of the authentication string (parameter-value pair). Initial data from the authentication string is preallocated by default for each authentication instance.

The authentication string is formatted as follows:

Module=<name>;<property1>=<value1>;<property2>=<value2>,...

Example:

Module=DialogUser;User=<user name>;Password=<password>

To specify initial data

1. In the Designer, select the **Base data > Security settings > Authentication modules** category.
2. Select the authentication module and enter the data in **Initial data**.

Syntax:

Property1=value1;Property2=value2

Example:

User=<user name>;Password=<password>

You can use different initial data depending on the authentication module.

Table 33: Initial data for authentication modules

Module Display Name	Authentication module	Parameters	Meaning/Comment
System users	DialogUser	User	User name.
		Password	User password.
Active Directory user account	ADSAccount		
Active Directory user account (dynamic)	DynamicADSAccount	Product	Use case. The system user is determined through the use case configuration data.
Active Directory user account (manual input)	DynamicManualADS	Product	Use case. The system user is determined through the use case configuration data.
		User	User name. The user's identity is determined from a predefined list of permitted Active Directory domains. In the TargetSystem ADS AuthenticationDomains configuration parameter, enter the permitted Active Directory domains.
		Password	User password.
Active Directory	RoleBasedADSAccount		No parameters required

Module Display Name	Authentication module	Parameters	Meaning/Comment
user account (role-based)			
Active Directory user account (manual input/role-based)	RoleBasedManualADS	User	User name. The user's identity is determined from a predefined list of permitted Active Directory domains. In the TargetSystem ADS AuthenticationDomains configuration parameter, enter the permitted Active Directory domains.
		Password	User password.
Employee	Employee	User	Employee's central user account.
		Password	User password.
Employee (dynamic)	DynamicPerson	Product	Use case. The system user is determined through the use case configuration data.
		User	User name.
		Password	User password.
Employee (role-based)	RoleBasedPerson	User	User name.
		Password	User password.
HTTP header	HTTPHeader	Header	HTTP Header to use.
		KeyColumn	Comma delimited list of key columns in the Person table to be searched for user names. Default: CentralAccount, PersonnelNumber
HTTP header (role-based)	RoleBasedHTTPHeader		HTTP header to use.
		KeyColumn	Comma delimited list of key columns in the Person table to be searched for user names. Default: CentralAccount, PersonnelNumber
LDAP user	DynamicLdap	User	User name.

Module Display Name	Authentication module	Parameters	Meaning/Comment
account (dynamic)			Default: CN, DistinguishedName, UserID, UIDLDAP
		Password	User password.
LDAP user account (role-based)	RoleBasedLdap	User	User name. Default: CN, DistinguishedName, UserID, UIDLDAP
		Password	User password.
Generic single sign-on (role-based)	RoleBasedGeneric	SearchTable	Table in which to search for the user name of the logged in user. This table must contain a FK named UID_Person that points to the Person table.
		SearchColumn	Column from the SearchTable in which to search for the user name of the logged-in user.
		DisabledBy	Pipe () delimited list of Boolean columns which block a user account from logging in.
		EnabledBy	Pipe () delimited list of Boolean columns which release a user account for logging in.
OAuth 2.0/OpenID Connect	OAuth		Dependent on the authentication method of the secure token service.
OAuth 2.0/OpenID Connect (role-based)	OAuthRoleBased		Dependent on the authentication method of the secure token service.
Account based system user	DialogUserAccountBased		No parameters required

Module Display Name	Authentication module	Parameters	Meaning/Comment
User account	QERAccount		No parameters required
User account (role-based)	RoleBasedQERAccount		No parameters required
Password reset	PasswordReset		No parameters required
Password reset (role-based)	RoleBasedPasswordReset		No parameters required
Decentralized identity	DecentralizedId	Email	Default email address of the employee (Person.DefaultEmailAddress) or contact email address of the employee (Person.ContactEmail)
		Identifier	Decentralized identity of the employee (Person.DecentralizedIdentifier).
Decentralized Identity (role-based)	RoleBasedDecentralizedId	Email	Default email address of the employee (Person.DefaultEmailAddress) or contact email address of the employee (Person.ContactEmail)
		Identifier	Decentralized identity of the employee (Person.DecentralizedIdentifier).

Related topics

- [Configuration data for system user dynamic authentication](#) on page 104
- [One Identity Manager authentication modules](#) on page 68

Configuration data for system user dynamic authentication

In the case of dynamic authentication modules, the system user assigned to the employee is not used for the log in. The system user which is configured using the user interface special configuration data is taken instead.

To specify configuration data

1. In the Designer, select the **Base data > Security settings > Programs** category.
2. Select the application and adjust the **Configuration data**.

Use XML syntax for entering the configuration data:

```
<DialogUserDetect>
  <Usermappings>
    <Usermapping
      DialogUser = "System user name"
      Selection = "Selection criterion"
    />
    <Usermapping
      DialogUser = "System user name"
    />
    ...
  </Usermappings>
</DialogUserDetect>
```

Enter the system user (DialogUser) in the Usermappings section. Specify which employee the given system user should use with the selection criterion (Selection). You are not obliged to enter a selection criterion for the assignment. The first system user that has the required assignment is used for the log in.

You can assign function groups to permissions groups on order to deal with complex permissions and user interface structures. The function groups allow you to map the functions an employee has in the company, for example, IT controller or branch manager. Assign the function groups to the permissions groups. A function group can refer to several permissions groups and several function groups can refer to one permissions group.

If the FunctionGroupMapping section is in the configuration data, this is evaluated first and the system user that is found is used. The authentication module uses the system user that is the exact member of the permissions group found for the login. If none is found, the Usermapping section is evaluated.

```
<DialogUserDetect>
  <FunctionGroupMapping
    PersonToFunction = "View mapping employee to function group"
```



```

        FunctionToGroup = "View mapping function group to permissions group"
    />
    <Usermappings>
        <Usermapping
            DialogUser = "System user name"
            Selection = "Selection criterion"
        />
        ...
    </Usermappings>
</DialogUserDetect>

```

Related topics

- [Example of a simple system user assignment on page 105](#)
- [Example of a system user assignment using a selection criterion on page 106](#)
- [Example of a function group assignment on page 107](#)
- [Granting One Identity Manager schema permissions through permissions groups on page 36](#)

Example of a simple system user assignment

All employees should be able to see the user interface for an IT Shop in a web front-end, without taking table and column permissions into account.

To do this, set up a new application, for example **WebShop_Customer_Prd**, and adapt the configuration data as follows:

```

<DialogUserDetect>
    <Usermappings>
        <Usermapping
            DialogUser = "dlg_all"
        />
    </Usermappings>
</DialogUserDetect>

```

Create a new **WebShop_Customer_Grp** permissions group, which receives the user interface for the application comprising the menu items, interface forms and task definitions. The user interface could consist of the following menu items:

- Employee contact data
- Requesting a product
- Unsubscribing a product

Define a new **dlg_all** system user and include it in the **vi_DE-CentralPwd**, the **vi_DE-ITShopOrder**, and the **WebShop_Customer_Grp** permissions groups.

Related topics

- [Configuration data for system user dynamic authentication](#) on page 104
- [Example of a system user assignment using a selection criterion](#) on page 106
- [Example of a function group assignment](#) on page 107
- [Granting One Identity Manager schema permissions through permissions groups](#) on page 36

Example of a system user assignment using a selection criterion

The scenario described in the previous example is extended such that only the cost center manager can see an employee's leaving date. You need to add the input field **LeavingDate** to the contact data form to do this.

Permissions are used for controlling viewing and editing. Set up a new **dlg_kst** system user and include the system user in the **vi_DE-CentralPwd**, **vi_DE-ITShopOrder** and **WebShop_Customer_Grp** permissions groups. You should also give the system user read and write permissions to the Person.Exitdate column.

Extend the application configuration data in such a way that the cost center managers use the **dlg_kst** system user to log in. All other employees use the **dlg_all** system user to log in.

Change the configuration data as follows:

```
<DialogUserDetect>
  <Usermappings>
    <Usermapping
      DialogUser = "dlg_kst"
      Selection = "select 1 where %uid% in (select uid_personhead from
profitcenter)"
    />
    <Usermapping
      DialogUser = "dlg_all"
    />
  </Usermappings>
</DialogUserDetect>
```

Related topics

- [Configuration data for system user dynamic authentication on page 104](#)
- [Example of a simple system user assignment on page 105](#)
- [Example of a function group assignment on page 107](#)
- [Granting One Identity Manager schema permissions through permissions groups on page 36](#)

Example of a function group assignment

To assign function groups to permissions groups you have to define two database views. The first database view shows the assignment of employees to function groups. The database view contains two columns, UID_Person and FunctionGroup.

Example:

```
create view custom_Person2Fu as
```

```
    select uid_personHead as UID_Person, 'Cost center manager' as FunctionGroup
    from Profitcenter
    where isnull(uid_personHead, '') > ' '
    union all
    select uid_personHead, 'Department manager' as FunctionGroup
    from Department
    where isnull(uid_personHead, '') > ' '
```

The second database view assigns function groups to permissions groups. This database view contains two columns, FunctionGroup and DialogGroup.

Example:

```
create view custom_Fu2D as
```

```
    select 'Cost center manager' as FunctionGroup, '<UID_Custom_Dialoggroup_ChefP>'
    as DialogGroup
    union all select 'Department manager', '<UID_Custom_Dialoggroup_ChefD>' as
    DialogGroup
```

Set up role-based permissions groups with the required permissions.

TIP: A role-based permissions group can inherit from a non role-based permissions group. This allows you to build up an inheritance hierarchy to making it easier to grant permissions.

Change the configuration data for assigning function groups to permissions groups as follows:

```
<DialogUserDetect>
    <FunctionGroupMapping
        PersonToFunction = "custom_Person2Fu"
```

```
        FunctionToGroup = "custom_Fu2D"  
    />  
</DialogUserDetect>
```

Related topics

- [Configuration data for system user dynamic authentication on page 104](#)
- [Example of a simple system user assignment on page 105](#)
- [Example of a system user assignment using a selection criterion on page 106](#)
- [Granting One Identity Manager schema permissions through permissions groups on page 36](#)

Checking authentication

When a user logs in, a validity check is run. Use the settings to configure additional options.

- The system runs additional validity checks to prevent users from working with established connections, if they were deactivated after they logged in. The check takes place with next action on the connection after a fixed interval of 20 minutes.

You can adjust the interval in the **Common | Authentication | CheckInterval** configuration parameter. In the Designer, edit the configuration parameter.

- The number of session that a user can open within a short time is limited to 10 session a minute.

If this number is exceeded, the user is sent an error message.

You have logged in too often in the last minute. Please wait a moment before you log in again.

This check is done for each front-end if the login is local. If the login is on the application server, it is checked for each application server.

You can modify the number of sessions in the **Common | Authentication | SessionsPerUserAndMinute** configuration parameter. In the Designer, edit the configuration parameter.

- Use the **QBM | AppServer | SessionTimeout** configuration parameter to add the timeout in hours, after which inactive application server sessions are closed. The default value is **24** hours. In the Designer, edit the configuration parameter.

OAuth 2.0 / OpenID Connect configuration

The **OAuth2.0/OpenID Connect** and **OAuth2.0/OpenID Connect (role-based)** authentication modules support the authorization code flow for OAuth 2.0 and OpenID Connect. For more information about the authorization code flow, see, for example, the [OAuth Specification](#) or the [OpenID Connect Specification](#).

To use OAuth2.0/OpenID Connect authentication

- In the Designer, create the identity provider and the OAuth2.0/OpenID Connect applications for the identity provider. A wizard is available in the Designer to assist in this process.
- Assign the OAuth2.0/OpenID Connect application to the web applications.

Related topics

- [Expiry of the OAuth 2.0/OpenID Connect authentication](#) on page 109
- [Creating the OAuth 2.0/OpenID Connect configuration](#) on page 111
- [Assigning OAuth 2.0/OpenID Connect configuration to web applications](#) on page 116
- [Specifying enabled and disabled columns for logging in](#) on page 118
- [OAuth 2.0/OpenID Connect](#) on page 87
- [OAuth 2.0/OpenID Connect \(role-based\)](#) on page 88
- [Logging information about OAuth 2.0/OpenID Connect authentication](#) on page 119

Expiry of the OAuth 2.0/OpenID Connect authentication

The web application (or client application) requests the authorization code at the authorization endpoint. The login endpoint is used to call an advanced login window, which

serves to determine the authorization code. The authentication module requires an access token from the token endpoint and the certificate is required to check the security token.

In the process, an attempt is made to find the certificate from the web application configuration. If this is not possible, the settings of the identity provider are used. To find the certificate for testing the token, the certificate stores are queried in the following order:

1. Configuration of the OAuth 2.0/OpenID Connect application (QBMSecurityClient table)
 - a. Certificate text (QBMSecurityClient.CertificateText).
 - b. Subject or thumbprint from the local memory (QBMSecurityClient.CertificateSubject and QBMSecurityClient.CertificateThumbPrint).
 - c. Certificate endpoint (QBMSecurityClient.CertificateEndpoint).
In addition, the subject or thumbprint is used to check certificates from the server if they are specified and do not exist locally on the server.
2. Configuration of the identity provider (QBMSecurityProvider table)
 - a. Certificate text ((QBMSecurityProvider.CertificateText).
 - b. Subject or thumbprint from the local memory (QBMSecurityProvider.CertificateSubject and QBMSecurityProvider.CertificateThumbPrint).
 - c. Certificate endpoint (QBMSecurityProvider.CertificateEndpoint)).
In addition, the subject or thumbprint is used to check certificates from the server if they are specified and do not exist locally on the server.
 - d. JSON-Web-Key endpoint (QBMSecurityProvider.JsonWebKeyEndpoint).

To identify the user account, the system determines which claim type is used to find the user information and which information from the One Identity Manager schema is used to find the user account.

Authentication through OpenID is built on OAuth 2.0. The OpenID Connect authentication uses the same mechanisms, but makes the claims available either in an ID token or with a UserInfo endpoint. Other configuration settings are required for using OpenID Connect. If the **Scope** contains the **openid** value, the authentication module uses OpenID Connect for authentication.

Related topics

- [Creating the OAuth 2.0/OpenID Connect configuration](#) on page 111
- [OAuth 2.0/OpenID Connect](#) on page 87
- [OAuth 2.0/OpenID Connect \(role-based\)](#) on page 88

Creating the OAuth 2.0/OpenID Connect configuration

To create an OAuth 2.0/OpenID Connect configuration

1. In the Designer, select the **Base data > Security settings > OAuth 2.0/OpenID Connect configuration** category.
2. Select the **Create a new identity provider** task.
3. On the start page of the wizard, click **Next**.
4. On the **New identity provider** page, enter the display name for the configuration and a description.
5. Click **Next**.
6. On the **Automatic configuration discovery** page, you define how you want to enter the information about the identity provider.
 - If the configuration data can be determined automatically by OpenID Connect Discovery:
 1. Select **Automatic configuration data discovery**.
 2. Enter the address (URL) for automatic determination of the configuration data in the input field, or select an example address through the selection menu.
 3. Click **Run**.
 4. The configuration data is determined and a dialog window is displayed. To accept the configuration data, click **OK**.
 - If you want to create the configuration data from a template:
 1. Select **Create from template file**.
 2. Click **Select** and choose the XML file.

For the One Identity Redistributable STS (RSTS), the file is pre-configured. You can find the RSTS_Template.xml in the One Identity Manager installation directory.
 3. Click **Open**.
 - If you do not want to determine the configuration data automatically, select **Manual data input**.

Enter the configuration data on the next page of the wizard.
7. Click **Next**.
8. On the **Configuration data** page, enter the general information for the database user.

NOTE: If you selected automatic determination of configuration data, some of the

information is already completed.

Table 34: General configuration data for the identity provider

Property	Description
Login endpoint	Uniform Resource Locator (URL) of the Secure Token Service login page. Example: http://localhost/rsts/login
Logout endpoint	URL of the log-out endpoint Example: http://localhost/rsts/login?wa=wsignout1.0
Token endpoint	Uniform Resource Identifier (URL) of the token endpoint of the authorization server for returning the access token to the client for logging in. Example: https://localhost/rsts/oauth2/token
Issuer	Uniform Resource Identifier (URI) of the certificate issuer for verifying the security token. Example: urn:STS/identity
Scope	Protocol for authentication. If the value is openid , OpenID Connect is used for authentication, otherwise OAuth 2.0 is used.
UserInfo endpoint	URL of the OpenID Connect UserInfo endpoint.
No ID token check	Specifies whether a check is made of the ID token. If the option is enabled, the ID token is not checked. The option can only be enabled for a scope containing the value openid and a populated UserInfo endpoint.
Self-signed certificates allowed	Specifies whether self-signed certificates are allowed for connecting to the token endpoint and UserInfo endpoint.
Shared Secret	Shared-Secret value used for authentication at the token endpoint. If all applications of the identity provider use the same Shared Secret, enter the value here. If the applications use different Shared Secrets, enter the Shared Secret values when creating the applications.
Requested authentication context class reference values	Space-delimited string specifying the acr values that the authorization server ought to use to process this authentication request, with the values appearing in order of preference.

9. Click **Next**.

10. On the **Configure certificates** page, enter the information for the identity provider's certificate. If all applications use the same certificate, enter the information here. If the applications use different certificate settings, enter the information when creating the application.

NOTE: If you selected automatic determination of configuration data, some of the information is already completed.

Table 35: Information about the identity provider certificate

Property	Description
Certificate endpoint	Uniform Resource Locator (URL) of the certificate end point on the authorization server. Example: https://localhost/RSTS/SigningCertificate
Subject of the certificate	Subject of the certificate used for verification. The subject or thumbprint must be set.
Thumbprint	Thumbprint of the certificate used to verify the security token.
JSON-Web-Key endpoint	URL of the JSON web key endpoint providing the token signing keys.
Certificate	Character string of the certificate content. It is used if no certificate is configured.

11. Click **Next**.
12. On the **Search rule for user information** page, you define how the login information is determined between the identity provider and the One Identity Manager database.

Table 36: Determining the login information

Property	Description
Value for the search	Full name of the claim type from which the login information is determined on the identity provider. Example: name of an entity http://schemas.xmlsoap.org/ws/2005/05/identity/claims/nameidentifier If you have determined the configuration data automatically, select a value from the list.
Column to search	Table and column in the One Identity Manager database in which the user information is stored. The table must contain a foreign key with the name UID_Person, which points to the Person table. Example: ADSAccount.ObjectGUID

Property	Description
User name value	<p>Full name of the claim type from which the user name is determined on the identity provider. The user name is used, for example, to identify data changes in One Identity Manager (XUserInserted and XUserUpdated columns).</p> <p>Example: User Principle Name (UPN)</p> <p>http://schemas.xmlsoap.org/ws/2005/05/identity/claims/upn</p> <p>If you have determined the configuration data automatically, select a value from the list.</p>
Value to check	Name of the claim type to be additionally checked. The claim type must appear under exactly this name in the token. The check ensures that only those people can log in whose token contains exactly the comparison value in the specified claim type.
Comparison value	Fixed value of the claim type specified under Value to check , against which is checked.

13. Click **Next**.

14. On the **Create OAuth 2.0/OpenID Connect applications** page, enter the application information for the identity provider.

a. Click  next to the **Applications** field.

To connect using RSTS, select **RSTS client**. Some of the information about the **RSTS client** application is already predefined.

b. On the **General** tab, enter the general information for the application.

Table 37: General information about the application

Property	Description
Display name	Display name of the application.
Description	Text field for additional explanation.
Client ID	<p>ID of the application on the identity provider. For client applications, enable the Default option.</p> <p>Example: urn:OneIdentityManager/Web</p>
Shared Secret	Application-specific Shared Secret value used for authentication at the token endpoint.
Resource to request	URN of the resource to be requested, for example for ADFS. Only required if the identity provider requires this value.

Property	Description
Redirect URL	Forwarding address for redirection of applications. Example: urn:InstalledApplication
Send post logout redirect URI	Specifies the behavior of the client after logging off from the application. Permitted values are Send post logout redirect URI (default), Do not send a redirect URI , and Send a specific redirect URI .
Post logout redirect URI	URI sent after logging off from the application.
Default	Specifies whether this is a standard application for client applications.

- c. On the **Certificate** tab, enter the information for the application certificate.

Table 38: Information about the application certificate

Property	Description
Certificate endpoint	Uniform Resource Locator (URL) of the certificate end point on the authorization server. Example: https://localhost/RSTS/SigningCertificate
Thumbprint	Thumbprint of the certificate used to verify the security token.
Subject of the certificate	Subject of the certificate used for verification. The subject or thumbprint must be set.
Certificate	Content of the certificate. It is used if no certificate is configured.

- d. On the **Authentication** tab, enter the following information

Table 39: Information about the application certificate

Property	Description
Authentication method	Authentication method at the token endpoint. Permitted values are: <ul style="list-style-type: none"> client_secret_basic (default value): HTTP basic authentication method. The Shared Secret is transferred in the HTTP header. client_secret_post: The Shared Secret is

Property	Description
	transferred in the client_secret value of the POST-Body.
	<ul style="list-style-type: none"> • none: No authentication at the token endpoint. • client_secret_jwt: The Shared Secret is transferred as a JSON web token (JWT). • private_key_jwt: The Shared Secret is transferred as JWT. In addition, encryption is carried out with the private key.
Token endpoint certificate	Hexadecimal thumbprint of the certificate for validating the token.
Requested authentication context class reference values	<p>Space-delimited string specifying the acr values that the authorization server ought to use to process this authentication request, with the values appearing in order of preference.</p> <p>If no reference values are defined here, the reference values of the identity provider are used.</p>

15. To create the identity provider and the application in the One Identity Manager database, click **Next**.
16. Click **Finish** to complete the wizard.

Related topics

- [Installing One Identity Redistributable STS](#) on page 132
- [Multi-factor authentication with One Identity Defender](#) on page 124

Assigning OAuth 2.0/OpenID Connect configuration to web applications

To use the **OAuth2.0/OpenID Connect** and **OAuth2.0/OpenID Connect (role-based)** authentication modules in One Identity Manager web applications, assign the OAuth2.0/OpenID Connect application to the web application.

To assign an OAuth2.0/OpenID Connect application to a web application

1. In the Designer, select the **Base data > Security settings > Web server configurations** category.
2. In List Editor, select the web application.

3. In the **Properties** edit view, assign the application in the **OAuth2.0/OpenID Connect application** selection list.
4. Select the **Database > Save to database** and click **Save**.

TIP: For some web applications, for example the Web Portal, you can customize the OAuth2.0/OpenID Connect configuration in the configuration file (web.config). For more information about configuring the Web Portal, see the *One Identity Manager Installation Guide*.

Displaying the configuration of the identity provider and the OAuth 2.0/OpenID Connect applications

To display the configuration of an identity provider

1. In the Designer, select the **Base data > Security settings > OAuth 2.0/OpenID Connect configuration** category.
2. In List Editor, select the identity provider. The configuration data is displayed on the following tabs in the edit view.
 - **General:** Displays the general configuration data of the identity provider.
 - **Certificate:** Shows the information about the identity provider certificate.
 - **Applications:** Displays the configuration of the OAuth 2.0/OpenID Connect applications.
 - **Columns for enabling:** Displays the table and the columns that identify a user account as activated.
 - **Columns for disabling:** Displays the table and the columns that identify a user account as deactivated.

To display the configuration of an OAuth 2.0/OpenID Connect application

1. In the Designer, select the **Base data > Security settings > OAuth 2.0/OpenID Connect configuration** category.
2. In List Editor, select the identity provider.
3. In the edit view, select the **Applications** tab.
4. To display the configuration of an application, select the OAuth 2.0/OpenID Connect application in the **Application** view.

NOTE:

Click on **Add** to add a new OAuth 2.0/OpenID Connect application to the configuration of the identity provider.

Click on **Remove** to remove an OAuth 2.0/OpenID Connect application that is no longer required from the configuration of the identity provider.

Related topics

- [Creating the OAuth 2.0/OpenID Connect configuration](#) on page 111
- [Specifying enabled and disabled columns for logging in](#) on page 118

Specifying enabled and disabled columns for logging in

In the determination of the user account for the OAuth 2.0/OpenID Connect authentication, the system checks whether the user account is enabled or disabled. You define which columns can mark a user account as enabled or disabled.

Note:

- Only the columns of the table that you selected in the OAuth 2.0/OpenID Connect configuration of the identity provider in the **Column to search** are displayed.
- A column can either be used as an enabled or a disabled column.
- You can specify just enabled columns or just disabled columns, or a combination of enabled and disabled columns.

Example:

A search column references the ADSAccount table.

Case a) Only enabled Active Directory user accounts are allowed to login.

- Select ADSAccount.AccountDisabled as the disabled column.

If the ADSAccount.AccountDisabled column of the user account is set, login is not permitted.

Case b) Only privileged Active Directory user accounts are allowed to login.

- Select ADSAccount.IsPrivilegedAccount as the enabled column.

If the ADSAccount.IsPrivilegedAccount column of the user account is set, login is permitted.

Case c) Only enabled, privileged Active Directory user accounts are allowed to login.

- Select ADSAccount.IsPrivilegedAccount as the enabled column and ADSAccount.AccountDisabled as the disabled column.

If the `ADSAccount.IsPrivilegedAccount` column of the user account is set and the `ADSAccount.AccountDisabled` column of the user account is not set, login is permitted.

To define which columns can enable a user account for login

1. In the Designer, select the **Base data > Security settings > OAuth 2.0/OpenID Connect configuration** category.
2. In the List Editor, select the configuration.
3. In the edit view, select the **Columns for enabling** tab.
4. In the **Add assignment** view, assign the columns that enable the user account for logon.
5. Select the **Database > Save to database** and click **Save**.

To define which columns can disable a user account for login

1. In the Designer, select the **Base data > Security settings > OAuth 2.0/OpenID Connect configuration** category.
2. In the List Editor, select the configuration.
3. Select the **Columns for disabling** tab in the edit view.
4. In the **Add assignment** view, assign the columns that disable the user account for logon.
5. Select the **Database > Save to database** and click **Save**.

Logging information about OAuth 2.0/OpenID Connect authentication

To support troubleshooting in OAuth 2.0/OpenID Connect authentication you can log personal login data, such as information about tokens or issuers. The log is written to the object log file (`<appName>_object.log`) of the respective One Identity Manager component.

To log authentication data

- In the Designer, set the **QBM | DebugMode | OAuth2 | LogPersonalInfoOnException** configuration parameter.

Multi-factor authentication in One Identity Manager

Table 40: Multi-factor authentication configuration parameters

Configuration parameter	Meaning
QER Person Defender	Specifies whether classic Starling Two-Factor Authentication integration is supported.
QER Person Defender ApiEndpoint	URL of the Starling 2FA API endpoint used to register new users.
QER Person Defender ApiKey	Your company's subscription key for accessing the Starling Two-Factor Authentication interface.
QER Person Starling	Specifies whether One Identity Starling Cloud is supported. Initiate your subscription within your One Identity on-prem product and join your on-prem solutions to our One Identity Starling Cloud platform. Giving your organization immediate access to a number of cloud-delivered microservices, which expand the capabilities of your One Identity on-prem solutions. We will continuously make available new products and features to our Starling Cloud platform. For a free trial of our One Identity Starling offerings and to get the latest product feature updates, visit cloud.oneidentity.com .
QER Person Starling ApiEndpoint	Token endpoint for logging in on the One Identity Starling platform. The value is determined by the Starling configuration wizard.
QER Person Starling ApiKey	Credential string for logging in on the One Identity Starling platform. The value is determined by the Starling configuration wizard.

You can set up multi-factor authentication for specific security-critical actions in One Identity Manager. You can use these, for example, for attestation or when approving requests in the Web Portal.

Use One Identity Manager One Identity Starling Two-Factor Authentication for multi-factor authentication. This service is normally provided over a One Identity Starling Cloud platform. If your company does not use a Starling Cloud, select the conventional Starling Two-Factor Authentication integration. Use configuration parameters to specify which of the two solutions are applied in your company.

To be able to use multi-factor authentication

1. Register your company in Starling Two-Factor Authentication.
For more information, see the Starling Two-Factor Authentication documentation.
2. Specify which authentication solution is used.
 - To use Starling Cloud
 1. Start the Launchpad.
 2. Select **Connection to Starling Cloud** and click **Run**.
This starts the Starling Cloud configuration wizard.
 3. Follow the Starling Cloud configuration wizard's instruction.

The configuration parameters under **QER | Person | Starling** are enabled and the authentication information is entered.
 - To use conventional Starling Two-Factor Authentication integration
 1. In the Designer, enable the **QER | Person | Defender** configuration parameter.
 - Enable the **QER | Person | Defender | ApiKey** configuration parameter and enter your company's subscription key as the value for accessing the Starling Two-Factor Authentication interface.

The default URL of the Starling 2FA API end point is already entered in the **QER | Person | Defender | ApiEndpoint** configuration parameter.
 3. Enable assigning by event for the PersonHasQERResource table. For more information, see [Editing table properties](#) on page 122.
 4. (Optional) Specify whether the security code must be requested from the Starling 2FA app. For more information, see [Requesting a security code](#) on page 123.
 5. In the Manager, enable the **New Starling 2FA token** service item. For more information, see [Preparing the Starling 2FA token request](#) on page 122.

If the user's telephone number has changed, cancel the current Starling 2FA token and request a new one. If the Starling 2FA token is no longer required, cancel it anyway.

For detailed information, see the following guides:

Theme	Guide
Preparing the IT Shop for multi-factor authentication	One Identity Manager IT Shop Administration Guide

Theme	Guide
Setting up multi-factor authentication for attestation	One Identity Manager Attestation Administration Guide
Setting up Starling Two-Factor Authentication in the web project	One Identity Manager Web Application Configuration Guide
Requesting the Starling 2FA Token	
Requesting products requiring multi-factor authentication	One Identity Manager Web Designer Web Portal User Guide
Approving requests with multi-factor authentication	
Attestation with multi-factor authentication	

Editing table properties

NOTE: If the **Assign by event** option is enabled, the `HandleObjectComponent` process is placed in the job queue as soon as a resource assignment is added to or removed from an employee.

To enable assigning by event for a table

1. In the Designer, select **One Identity Manager Schema**.
2. Select the `PersonHasQERRResource` table and start Schema Editor using the **Show table definition** task.
3. In the **Table properties** view, select the **Table** tab and enable the **Assign by event** option.
4. Select the **Database > Save to database** and click **Save**.

For more information about editing table definitions, see the *One Identity Manager Configuration Guide*.

Preparing the Starling 2FA token request

One Identity Manager users must be registered with Starling Two-Factor Authentication in order to use multi-factor authentication. To register, a user must request the Web Portal Token in the Starling 2FA. Once the request has been granted approval, the user receives a link to the Starling Two-Factor Authentication app and a Starling 2FA user ID. The app generates one-time passwords, which are required for authentication. The Starling 2FA user ID is saved in the user's employee main data.

NOTE: The user's default email address, mobile phone and country must be stored in their main data. This data is required for registering.

To facilitate requesting a Starling 2FA token

1. In the Manager, select the **IT Shop > Service catalog > Predefined** category.
2. Select **New Starling 2FA token** in the results list.
3. Select the **Change main data** task.
4. Disable **Not available**.
5. Save the changes.

The Starling 2FA token request must be granted approval by the request recipient's manager.

Requesting a security code

Table 41: Configuration parameter for requesting Starling 2FA security codes

Configuration parameter	Meaning
QER Person Defender DisableForceParameter	The configuration parameters specify whether Starling 2FA is forced to send the security code by SMS or phone call if one of these options is selected for multi-factor authentication. If the configuration parameters are enabled, Starling 2FA can refuse this request; the user must then request the security code by the Starling 2FA app.
QER Person Starling DisableForceParameter	

If the security code is requested for an attestation, request, or request approval, the user decides how the security code is sent. The following options are available:

- By Starling 2FA app
- By SMS
- By phone call

By default, Starling 2FA is forced to send the security code by SMS or by phone call if the user has selected one of these options. However, for security reasons, the user should use the Starling 2FA app to generate the security code. If the app is installed on the user's mobile phone, Starling 2FA can refuse the SMS or phone demand and the user must generate the security code using the app.

To use this method

- If you use Starling Cloud, in the Designer, set the **QER | Person | Starling | DisableForceParameter** configuration parameter.
- OR -

- If you use classic Starling Two-Factor Authentication integration, in the Designer, set the **QER | Person | Defender | DisableForceParameter** configuration parameter.

Starling 2FA can refuse to transmit the security code by SMS or phone call if the Starling 2FA app is installed on the phone. Then the security code must be generated by the app.

If the configuration parameter is not set (default), Starling 2FA is forced to send the security code by SMS or phone call.

Multi-factor authentication with One Identity Defender

One Identity Defender can be used for multi-factor authentication on One Identity Manager tools and the Web Portal . A Redistributable STS (RSTS) is set up to provide Active Directory authentication over a RADIUS server.

Prerequisite

- One Identity Defender is installed and set up.

To set up multi-factor authentication using Defender

1. Install the RSTS.

In the Installation Wizard on the **Installation Settings** page, enter the signing certificate, URL, and configuration password for the RSTS administration interface. For test or demonstration environments, you can use the **Redistributable STS Demo** signing certificate.

2. Configure the RSTS.
3. Set up the OAuth 2.0/OpenID Connect configuration.

In doing so, you create a new identity provider. You will need this identity provider for configuring authentication with OAuth 2.0/Openid Connect.

4. Configure authentication with OAuth 2.0/Openid Connect for the Web Portal.
5. Configure authentication with OAuth 2.0/OpenID Connect for the One Identity Manager administration tools.

6. Test the access to the Web Portal.

- After entering the URL of the Web Portals in your web browser, you should be redirected to the RSTS login page.
- After logging in with user name and password, you are prompted to enter your Defender Token.

If both authentications were successful, you can work with the Web Portal.

7. Test access to the One Identity Manager administration tools.

- Start an administration tool, for example, the Launchpad, and select the **OAuth 2.0/OpenID Connect** authentication method.
- After logging in with user name and password, you are prompted to enter your Defender Token.

If both authentications were successful, you can work with the administration tool.

Detailed information about this topic

- [Installing One Identity Redistributable STS](#) on page 132
- [Configuring RSTS for multi-factor authentication](#) on page 125
- [Creating the OAuth 2.0/OpenID Connect configuration](#) on page 111
- [Configuring authentication with OAuth 2.0/OpenID Connect in the Web Portal](#) on page 126
- [Configuring authentication with OAuth 2.0/OpenID Connect](#) on page 127

Configuring RSTS for multi-factor authentication

To configure multi-factor authentication using a RADIUS server on the RSTS

1. Start a web browser and open the URL of the RSTS administration interface.
https://<webapplication>/RSTS/admin
Use the configuration password assigned during installation to log in.
2. On the home page, click **Authentication providers**.
3. On the **Authentication Providers** page, select the **Default Active Directory** default provider and click ☒ **Edit**.
4. On the **Edit** page, select the **Authentication provider** tab and edit the following settings.
 - **Directory Type > Active Directory**: enabled
 - **Connection Information > Use Current Domain**: enabled
5. Select the **Two Factor Authentication** tab and edit the settings for your Defender Security Server.
 - **Two Factor Authentication Settings > RADIUS**: enabled
 - **Server, Port, Shared Secret** and **Username Attributes**: Connection data for the RADIUS server.
 - (Optional) **Connection Information > Pre-authenticate For ChallengeResponse**: Uses the response text of the defender, instead of the default RADIUS response text.
6. Switch to the home page and select **Applications**.

7. On the **Applications** page, click **Add Application**.
8. On the **Edit** page, select the **General Settings** tab and edit the following settings.
 - **Application Name, Authentication Provider, Realm/Client_ID/Issuer, Redirect Url**

The redirect URL for the Web Portal (**Redirect Url**) is formed as follows:
`https://<Server>/<Application Name>/`

9. Select the **Certificates** tab and under **Signing Certificate (Required)** activate the signing certificate that you specified when installing the RSTS.

For more information, see [Multi-factor authentication with One Identity Defender](#) on page 124.


10. Click **Finish**.

Related topics

- [Installing One Identity Redistributable STS](#) on page 132

Configuring authentication with OAuth 2.0/OpenID Connect in the Web Portal

To configure authentication with OAuth 2.0/OpenID Connect

1. Start the Web Designer.
2. Click the **View > Home page** menu item.
3. On the home page, click **Select web application** and select the web application.
4. Click  **Edit web application settings**.
5. In the **Edit web application settings** dialog, edit the web application settings.
 - **Authentication module:** Select **OAuth 2.0/OpenID Connect (role-based)**.
 - **OAuth 2.0/OpenID Connect configuration:** Select the newly created identity provider.
 - **Client ID for OAuth 2.0 authentication:** Select the client ID that you specified when you configured RSTS.
 - **Fingerprint of the OAuth 2.0 certificate:** Specify the fingerprint of the signing certificate you selected when configuring the RSTS.
6. Save the changes.

Related topics

- [Multi-factor authentication with One Identity Defender](#) on page 124
- [Configuring RSTS for multi-factor authentication](#) on page 125

- [Configuring authentication with OAuth 2.0/OpenID Connect on page 127](#)
- [Creating the OAuth 2.0/OpenID Connect configuration on page 111](#)

Configuring authentication with OAuth 2.0/OpenID Connect

To configure authentication with OAuth 2.0/OpenID Connect

1. In the Designer, select the **Base data > Security settings > OAuth 2.0/OpenID Connect configuration** category.
2. In the list editor, select the newly created identity provider.
3. Select the **General** tab and check the general configuration data of the identity provider.
 - **Column to search:** Select **ADSAccount - ObjectGUID**.
4. Select the **Applications** tab and check the configuration of the OAuth 2.0/OpenID Connect application.
 - **Default:** enabled
 - **Redirect URI:** If you want to use multifactor authentication with the administration tools of the One Identity Manager, enter **urn:InstalledApplication**.
5. Select the **Database > Save to database** and click **Save**.

Related topics

- [Multi-factor authentication with One Identity Defender on page 124](#)
- [Configuring authentication with OAuth 2.0/OpenID Connect in the Web Portal on page 126](#)
- [Configuring RSTS for multi-factor authentication on page 125](#)
- [Creating the OAuth 2.0/OpenID Connect configuration on page 111](#)

Authenticating other applications using OAuth 2.0/OpenID Connect

For more information about the REST API, see the *One Identity Manager REST API Reference Guide*.

To access the REST API in the application server, authentication is supported by the **OAuth2.0/OpenID Connect** and **OAuth2.0/OpenID Connect (role-based)** authentication modules.

Authentication is done using the access token provided. The first time a request is made with a new access token, a session is established with that token and the authentication module. Further accesses with the same token use the same session. The validity period of the token is checked in the process.

To set up external application authentication using OAuth 2.0/OpenID Connect in One Identity Manager

- In the Designer, set the **QBM | AppServer | AccessTokenAuth** configuration parameter.
- In the Designer, set the respective authentication module either **OAuth 2.0/OpenID Connect** or **OAuth 2.0/OpenID Connect (role-based)**.
- In the Designer, set up the OAuth 2.0/OpenID Connect configuration.
- If the **OAuth 2.0/OpenID Connect (role-based)** authentication module is used, set the **QBM | AppServer | AccessTokenAuth | RoleBased** configuration parameter as well.
- The URL for the application server must be declared.

When the application server is installed, an entry for the web application is created with the URL in the QBMWebApplication table. Check whether the URL (BaseUrl column) is entered.

To display a web application's settings

1. In the Designer, select the **Base data > Security settings > Web server configurations** category.
2. In List Editor, select the web application.

To authenticate an external application using OAuth 2.0/OpenID Connect in One Identity Manager

1. Log in to the external identity provider, for example with Redistributable STS (RSTS), and get the access token.
2. Ensure that the token is passed as the bearer token in the authentication header of all queries.

NOTE: The session must be handled by a bearer token when logging in using a session cookie. Clients accessing the REST API using the bearer token must therefore keep the cookie assigned during the first access and send it with subsequent accesses. Otherwise, a new session is established for each access, which costs a lot of resources.

Related topics

- [OAuth 2.0/OpenID Connect](#) on page 87
- [OAuth 2.0/OpenID Connect \(role-based\)](#) on page 88
- [Expiry of the OAuth 2.0/OpenID Connect authentication](#) on page 109
- [OAuth 2.0 / OpenID Connect configuration](#) on page 109

Granular permissions for the SQL Server and database

To implement a One Identity Manager database or a One Identity Manager History Database on a SQL Server or a managed instance in Azure SQL Database, you are provided with SQL Server logins and database users for administrative users, configuration users and end users. Permissions at server and database level are matched to suit the user's tasks.

Normally, you cannot edit users and permissions. It may be necessary to set up an additional database user to use a One Identity Manager History Database.

For more information about users and their permissions, see the *One Identity Manager Installation Guide*, and the *One Identity Manager Data Archiving Administration Guide*.

Related topics

- [Displaying database server logins](#) on page 130
- [Displaying users' access levels](#) on page 131
- [Displaying server roles and database roles permissions](#) on page 131
- [Minimum access levels of One Identity Manager tools](#) on page 136

Displaying database server logins

To display login information

1. In the Designer, select the **Base data > Security settings > Database server permissions > Database server login** category.
2. Select the database server login. The following information is displayed:
 - **Login name:** The user's SQL Server login.
 - **Database server login:** Type of database user.


- **Access level:** The access level for logging in. The access levels displayed are **End user**, **Configuration user**, **Administrative user**, **System administrator**, and **Unknown**.
3. To show the database roles and server roles that are assigned, select the **Database or server role** tab.

Displaying users' access levels

NOTE:

- If you select an existing database connection in the connections dialog, the access level of the login to be used is shown in a tooltip.
- Some user interfaces expect configuration user permissions at least. Logging in as an end user is not possible in this case.

To find the access level of the logged in user

- To display user information, double-click the icon in the program status bar 
On the **System user** tab, in the **SQL access level** field, you will see the access level for the current login. The access levels displayed are **End user**, **Configuration user**, **Administrative user**, **System administrator**, and **Unknown**.

Related topics

- [Displaying database server logins](#) on page 130

Displaying server roles and database roles permissions

Server and database permissions are predefined and cannot be modified.

| **NOTE:** The **End user role** database role is permitted for custom schema extensions.

To display server and database permissions

- In the Designer, select server role or the database role in the **Base data > Security settings > Database server permissions > Database server login** category.

This opens the List Editor showing a list of permissions.

Installing One Identity Redistributable STS

The Redistributable STS (RSTS) is a Secure Token Server component service designed to provide user authentication using standard federation protocols such as WS-Federation and OAuth 2.0. One Identity Manager uses the RSTS for authentication to web applications with Webauthn and OAuth 2.0.

For detailed information about the Webauthn configuration, see the *One Identity Manager Web Application Configuration Guide*.

To install the RSTS

1. Launch `autorun.exe` from the root directory of the One Identity Manager installation medium.
2. Switch to the **Other products** tab
3. Select **One Identity Redistributable STS** and click **Install**.
4. On the start page of the installation wizard, click **Next**.
5. On the **Select database** page, select the One Identity Manager database connection. Select a user who has a minimum of administrative permissions for the database.
6. On the **Installation settings** page, enter the required information.
7. On the **Installation** page you can see the installation progress. When the installation has finished, click **Next**.
8. Click **Finish** to close the installation wizard.

Related topics

- [OAuth 2.0/OpenID Connect](#) on page 87
- [OAuth 2.0 / OpenID Connect configuration](#) on page 109
- [Multi-factor authentication with One Identity Defender](#) on page 124

Program functions for starting the One Identity Manager tools

The One Identity Manager tools can only be started if the user has the relevant program function permissions. The following program functions allow the One Identity Manager tools to be started.

To make the program function available to users

- In the Designer under the **Permissions > Program functions** category, check which permissions group contains the required program function and assign the program functions to other permissions groups as necessary.
- For non role-based login: Add the system user to the permissions group in the Designer under **Permissions > System users**.
- For role-based logins: Ensure that the user is assigned to the application role that owns the program function through its permissions group.

Table 42: Program functions for starting the One Identity Manager tools

Program function	Description
ApplicationStart_Analyzer	Allows the program Analyzer (Analyzer.exe) to be started.
ApplicationStart_ApiDesigner	Allows the program API Designer (ApiDesigner.exe) to be started.
ApplicationStart_ConfigWizard	Allows the program Configuration Wizard (ConfigWizard.exe) to be started.
ApplicationStart_CryptoConfig	Allows the program Crypto Configuration (CryptoConfig.exe) to be started.
ApplicationStart_DataImporter	Allows the program Data Import (DataImporter.exe) to be started.
ApplicationStart_DBClone	Allows the program (DBCclone.exe) to be started.
ApplicationStart_DBComparer	Allows the program (DBComparer.exe) to be started.

Program function	Description
ApplicationStart_DBCompiler	Allows the program Database Compiler (DBCompiler.exe) to be started.
ApplicationStart_Designer	Allows the program Designer (Designer.exe) to be started.
ApplicationStart_JobQueueInfo	Allows the program Job Queue Info (JobQueueInfo.exe) to be started.
ApplicationStart_LaunchPad	Allows the program Launchpad (LaunchPad.exe) to be started.
ApplicationStart_LicenseMeter	Allows the program License Meter (LicenseMeter.exe) to be started.
ApplicationStart_Manager	Allows the program Manager (Manager.exe) to be started.
ApplicationStart_ObjectBrowser	Allows the program Object Browser (ObjectBrowser.exe) to be started.
ApplicationStart_OpSupport	Enables start-up of the Operations Support Web Portal.
ApplicationStart_ReportEdit	Allows the program Report Editor (ReportEdit2.exe) to be started.
ApplicationStart_SchemaExtension	Allows the program Schema Extension (SchemaExtension.exe) to be started.
ApplicationStart_ServerInstaller	Allows the program Server Installer (ServerInstaller.exe) to be started.
ApplicationStart_SoftwareLoader	Allows the program Software Loader (SoftwareLoader.exe) to be started.
ApplicationStart_SynchronizationEditor	Allows the program Synchronization Editor (SynchronizationEditor.exe) to be started.
ApplicationStart_SystemDebugger	Allows the program System Debugging (SystemDebugger.exe) to be started.
ApplicationStart_Transporter	Allows the program Database Transporter (Transporter.exe) to be started.
ApplicationStart_WebDesignerCompiler	Allows the program (VI.WebDesigner.CompilerCmd.exe) to be started.
ApplicationStart_WebConfig	Allows the program Web Designer Configuration Editor (WebConfigEditor.exe) to be started.
ApplicationStart_WebDesigner	Allows the program Web Designer (WebDesigner.exe) to be started.
ApplicationStart_WebDesignerInstall	Allows the program Web Installer (WebDesigner.Installer.exe) to be started.

Related topics

- [Assigning program functions to permissions groups on page 64](#)
- [Adding system users to permission groups on page 50](#)
- [Assigning employees to application roles on page 30](#)

Minimum access levels of One Identity Manager tools

NOTE:

- Connections that do not use the expected access level for SQL Server logins are not shown in the connection dialog.
- If you select an existing database connection in the connections dialog, the access level of the login to be used is shown in a tooltip.

You require the following minimum access level for One Identity Manager tools.

Table 43: Access level for One Identity Manager tools

Tool	Minimum access level
Analyzer	End user
Application server	End user or configuration user (depending on the application server's task)
AppServer.Installer.CMD.exe	Configuration user
API Designer	Configuration user
API Server	End user
Configuration Wizard	Administrative user
Crypto Configuration	Configuration user
Data Import	End user Configuration user (saves import definition)
DataImporterCMD.exe	End user
Database Compiler	Configuration user
DBCompilerCMD.exe	Configuration user
Database Transporter	Configuration user

Tool	Minimum access level
DBTransporterCMD.exe	Administrative user
DBClone	Administrative user
DBComparer	Configuration user
Designer	Configuration user Some consistency checks require the administrative user access level.
Job Queue Info	Configuration user
Launchpad	End user Some application that are started from the Launchpad, required different access levels
License Meter	End user
Manager	End user Some functions require configuration user access levels, for example, opening synchronization projects for target systems. Some consistency checks require the configuration user or administrative user access level.
HistoryDB Manager	End user
Object Browser	End user
One Identity Manager Service	Configuration users for process collection with the MSSQLJobProvider
Report Editor	Configuration user
Schema Extension	Configuration user
SchemaExtensionCmd.exe	Configuration user
Server Installer	Configuration user
Software Loader	Configuration user
SoftwareLoaderCMD.exe	Configuration user
Synchronization Editor	Configuration user
System Debugger	Configuration user
Web Designer	Configuration user
Web Designer Configuration Editor	Configuration user

Tool	Minimum access level
VI.WebDesigner.CompilerCmd.exe	Configuration user
WebDesigner.InstallerCMD.exe	Configuration user
Web Portal	End user
Password Reset Portal	End user
Operations Support Web Portal	End user
Quantum.MigratorCmd.exe	Administrative user

Related topics

- [Granular permissions for the SQL Server and database](#) on page 130

One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

Contacting us

For sales and other inquiries, such as licensing, support, and renewals, visit <https://www.oneidentity.com/company/contact-us.aspx>.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at <https://support.oneidentity.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to videos at www.YouTube.com/OneIdentity
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product

A

- application role 8
 - administrators 10, 13, 15-19, 21, 23-24, 26
- Application Governance 26
 - administrators 26
 - approver 26
 - owner 26
- approver 18-19
- approver (IT) 18-19
- asset and account owners 25
- assign employees 30, 32
- assign extended properties 34
- assign reports 33
- attestation policy owner 16
- attestor for external users 16
- attestors 13, 15, 18-19, 21
- auditors 13
- authorize as One Identity Manager administrator 27
- base roles 10, 12
 - administrators 10, 27
 - employee manager 10
 - everyone (change) 10
 - everyone (Change) 10
 - internal permissions 10
 - operational support 12
 - password help desk 12
 - synchronization post-processing 12
- chief approval team 16, 21
- cloud administrators 24
- Compliance and Security Officer 12
- conflicting 33
- custom 26
 - administrators 26
 - manager 26
- dynamic 32
- edit 28-29
- employee manager 10
- exception approver 15
- extend permissions 31
- Identity and Access Governance 12-13, 15-17
 - attestation 16
 - administrators 16
 - attestation policy owner 16
 - chief approval team 16
- auditors 13
- company policies 15
 - administrators 15
 - attestors 15
 - exception approver 15
 - policy supervisors 15
- Compliance & Security Officers 12
- Identity Audit 13
 - administrators 13
 - attestors 13
 - maintain SAP function 13
 - rule supervisor 13
- subscribable reports 17
 - administrators 17

- Identity Management 18
 - business roles 18
 - administrators 18
 - approver 18
 - approver (IT) 18
 - attestors 18
 - employees 21
 - administrators 21
 - management level 18
 - organizations 19
 - administrators 19
 - approver 19
 - approver (IT) 19
 - attestors 19
 - internal permissions 10
 - management level 18
 - overview 9
 - permissions group 29, 31
 - policy supervisors 15
 - Privileged Account Governance 25
 - product owners 21
 - put into operation 27
 - report 35
 - Request and Fulfillment 21
 - IT Shop 21
 - administrators 21
 - attestors 21
 - chief approval team 21
 - product owners 21
 - rule supervisor 13
 - self-registered employees 10
 - target system
 - administrators 23
 - target system managers 23
 - target system managers 23
 - Universal Cloud Interface
 - administrators 24
 - assignment resource
 - for an application role 35
 - authentication
 - test 108
 - authentication module
 - account-based system user 75
 - Active Directory user account 76
 - Active Directory user account (dynamic) 80
 - Active Directory user account (manual entry/role based) 79
 - Active Directory user account (manual) 78
 - Active Directory user account (role based) 77
 - assign application 97-98
 - component authenticator 90
 - Crawler 91
 - decentralized identity 94
 - decentralized identity (role-based) 95
 - employee 71
 - employee (dynamic) 73
 - employee (role based) 72
 - enable 97
 - generic single sign-on (role based) 69
 - HTTP header 85
 - HTTP header (role based) 86
 - initial data 99
 - LDAP user account (dynamic) 83
 - LDAP user account (role based) 81
 - OAuth 2.0/OpenID Connect 87
 - OAuth 2.0/OpenID Connect (role-based) 88

- password reset (role-based) 93
- reset password 91
- synchronization authenticator 89
- system user 69
- user account 74
- User Account (role based) 74
- Web Agent authenticator 90

D

- database
 - authorizations 130
- database role
 - display permissions 131
- database server
 - access level 130
 - authorizations 130
 - database user 130
 - login 130
- dynamic role
 - application role 32

E

- employee
 - authorize as One Identity Manager administrator 27
- event
 - object event 66
 - program function 66

I

- install RSTS 132

L

- Launchpad
 - action
 - program function 67

M

- method definition
 - program function 65
- Multi-factor authentication 120

O

- OAuth 2.0/OpenID Connect
 - authentication 109
 - authentication module 87-88
 - certificate 111
 - configurations 109, 111, 117
 - disabling columns 118
 - enabling columns 118
 - external application 128
 - identity provider 111, 117
 - openid 111
 - scope 111
 - shared secret 111
 - use case 111, 117
 - Web application 116
- object
 - authorizations 60
- object event 66
 - program function 66
- One Identity Starling 120

P

permission

- column permission 56
- copy 57
- database 130
- database role 131
- determine 39
- edit 53
- object 60
- permissions filter 55
- permissions group 53
- rules 39
- server role 131
- simulation 58
- SQL Server 130
- table 54
- table permissions 55
- user 61

Permissions Editor 53

permissions group

- assign application 61
- assign to employee 43-44
- authorizations 53
- copy 45
- hierarchy 43
- only for role-based login 47
- predefined 37
- program function 64-66
- QBM_BaseRights 37
- QER_OperationsSupport 37
- role based 37
- set up 42, 46-47
- vi_4_ADMIN_LOOKUP 37
- VI_4_ALLUSER 37

VI_Everyone 37

VI_View 37

vid 37

VID_Features 37

program function 63-64, 66

Launchpad actions 67

method definition 65

permissions group 64-66

script 64

R

RADIUS Server 124

redistributable STS 132

RSTS 124

S

script

permission 64

program function 64

Secure Token Server 132

security code

demand

by app 123

by call 123

by text 123

server role

display permissions 131

Starling 2FA 120, 122

Starling 2FA security code 123

Starling Cloud 120

Starling Cloud security code 123

Starling Two-Factor Authentication 120

system user

administrative user 49

- determine dynamically 104
- dynamic 37, 52
- employees 52
- logins 49
- password 49
- password never expires 49
- permissions group 50
- predefined 37
- Read-only permissio 49
- sa 37
- service account 49
- set up 47-48
- support 37
- Synchronization 37
- user 52
- viadmin 37
- viHelpdesk 37
- program function 61
- read permissions 61
- system user 61

T

- table
 - authorizations 54
- token 122

U

- use case
 - assign authentication module 97-98
 - assign permissions group 61
 - configuration data 104
- user
 - access level 131
 - authentication module 61
 - authorizations 61
 - dynamic 61
 - permissions group 61