



One Identity Manager 8.2.1

Administration Guide for Connecting to Exchange Online

Copyright 2022 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC.

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC.
Attn: LEGAL Dept
4 Polaris Way
Aliso Viejo, CA 92656

Refer to our Web site (<http://www.OneIdentity.com>) for regional and international office information.

Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <http://www.OneIdentity.com/legal/patents.aspx>.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.OneIdentity.com/legal. All other trademarks are the property of their respective owners.

Legend

 **WARNING:** A WARNING icon highlights a potential risk of bodily injury or property damage, for which industry-standard safety precautions are advised. This icon is often associated with electrical hazards related to hardware.

 **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.

One Identity Manager Administration Guide for Connecting to Exchange Online
Updated - 03 June 2022, 02:55
Version - 8.2.1

Contents

About this guide	9
Managing Exchange Online environments	10
Architecture overview	10
One Identity Manager users for managing Exchange Online	11
Configuration parameters for managing Exchange Online environments	13
Synchronizing an Exchange Online environment	14
Setting up Exchange Online synchronization	15
Users and permissions for synchronizing with Exchange Online	16
Installing the Exchange Online PowerShell V2 module	17
Setting up the Exchange Online synchronization server	18
System requirements for the Exchange Online synchronization server	18
Installing One Identity Manager Service with an Exchange Online connector	19
Preparing the administrative workstation for access to Exchange Online	22
Preparing a remote connection server for access to Exchange Online	22
Creating a synchronization project for initial synchronization of an Exchange Online environment	23
Information required for Exchange Online synchronization projects	24
Creating an initial synchronization project for Exchange Online	25
Exchange Online synchronization features	28
Configuring the synchronization log	30
Customizing the synchronization configuration	31
How to configure Exchange Online synchronization	32
Changing system connection settings of Exchange Online	32
Editing connection parameters in the variable set	33
Editing target system connection properties	34
Advanced settings for the Exchange Online connector	35
Updating schemas	37
Speeding up Exchange Online synchronization with revision filtering	38
Configuring the provisioning of memberships	40
Configuring single object synchronization	41
Accelerating provisioning and single object synchronization	42

Running synchronization	43
Starting synchronization	44
Deactivating synchronization	45
Displaying synchronization results	45
Synchronizing single objects	46
Tasks following synchronization	47
Post-processing outstanding objects	47
Adding custom tables to the target system synchronization	49
Managing Exchange Online mail users and Exchange Online mail contacts through account definitions	50
Troubleshooting	50
Ignoring data error in synchronization	51
Basic data for managing an Exchange Online environment	53
Account definitions for Exchange Online mail users and Exchange Online mail contacts	54
Creating account definitions	55
Editing account definitions	56
Main data for account definitions	56
Editing manage levels	58
Creating manage levels	59
Assigning manage levels to account definitions	60
Main data for manage levels	60
Creating mapping rules for IT operating data	61
Entering IT operating data	62
Modify IT operating data	63
Assigning account definitions to employees	64
Assigning account definitions to departments, cost centers, and locations	66
Assigning account definitions to business roles	66
Assigning account definitions to all employees	67
Assigning account definitions directly to employees	68
Assigning account definitions to system roles	68
Adding account definitions in the IT Shop	69
Assigning account definitions to Azure Active Directory tenants	71
Deleting account definitions	71
Target system managers for Exchange Online	74
Job server for Exchange Online-specific process handling	76

General main data for Job servers	77
Specifying server functions	79
Exchange Online organization configuration	82
Extensions for Azure Active Directory tenants	82
Exchange Online public folders	83
Exchange Online policies	84
Exchange Online mailboxes	86
Creating Exchange Online mailboxes	87
Editing main data of Exchange Online mailboxes	88
General main data for Exchange Online mailboxes	89
Limits and usage of Exchange Online mailboxes	91
Policies and features of Exchange Online mailboxes	92
Booking resources for Exchange Online equipment mailboxes and Exchange Online room mailboxes	95
Booking permissions for Exchange Online equipment mailbox and Exchange Online room mailbox	97
Adjusting receive restrictions for Exchange Online mailboxes	98
Customizing send permissions for Exchange Online mailboxes	99
Specifying moderators for Exchange Online mailboxes	100
Assigning extended properties to Exchange Online mailbox	100
Deleting Exchange Online mailboxes	101
Exchange Online mail users	102
Creating Exchange Online mail users	103
Editing main data of Exchange Online mail users	103
Main data for Exchange Online mail users	104
Receive restrictions for Exchange Online mail users	109
Customizing send permissions for Exchange Online mail users	109
Specifying moderators for Exchange Online mail users	110
Assigning extended properties to Exchange Online mail users	111
Deleting Exchange Online mail users	111
Exchange Online mail contacts	112
Creating Exchange Online mail contacts	113
Editing main data of Exchange Online mail contacts	113
Main data for Exchange Online mail contacts	114

Receive restrictions for Exchange Online mail contacts	118
Customizing send permissions for Exchange Online mail contacts	119
Specifying moderators for Exchange Online mail contacts	120
Assigning extended properties to Exchange Online mail contacts	120
Deleting Exchange Online mail contacts	121
Exchange Online mail-enabled distribution groups	122
Creating Exchange Online mail-enabled distribution groups	123
Editing main data for Exchange Online mail-enabled distribution groups	123
Main data for Exchange Online mail-enabled distribution groups	124
Receive restrictions for Exchange Online mail-enabled distribution groups	127
Customizing send permissions for Exchange Online mail-enabled distribution groups	127
Specifying moderators for Exchange Online mail-enabled distribution groups	128
Specifying Exchange Online mail-enabled distribution groups	129
Assigning Exchange Online mail-enabled distribution groups to Exchange Online recipients	129
Prerequisites for indirect assignment of Exchange Online mail-enabled distribution groups	131
Assigning Exchange Online mail-enabled distribution groups to departments, cost centers, and locations	132
Assigning Exchange Online mail-enabled distribution groups to business roles	134
Adding Exchange Online mail-enabled distribution groups to system roles	135
Assigning Exchange Online mail-enabled distribution groups to the IT Shop	136
Adding Exchange Online mail-enabled distribution groups automatically to the IT Shop	137
Assigning Exchange Online recipients to Exchange Online mail-enabled distribution groups	139
Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mailboxes	140
Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mail users	141
Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mail contacts	142
Exchange Online mail-enabled distribution group inheritance based on categories	142
Adding Exchange Online dynamic distribution groups to Exchange Online mail-enabled distribution groups	143
Adding an Exchange Online dynamic distribution group to Exchange Online mail-enabled distribution groups	144

Adding Exchange Online mail-enabled public folder to Exchange Online mail-enabled distribution groups	144
Assigning extended properties to Exchange Online mail-enabled distribution groups ..	145
Deleting Exchange Online mail-enabled distribution groups	145
Exchange Online Office 365 groups	147
Creating Exchange Online Office 365 groups	147
Editing main data of Exchange Online Office 365 groups	148
Exchange Online Office 365 group main data	148
Customizing receive restrictions for Exchange Online Office 365 groups	152
Assigning owners to Exchange Online Office 365 groups	153
Assigning subscribers to Exchange Online Office 365 groups	154
Assigning Exchange Online Office 365 groups to Azure Active Directory user accounts	154
Prerequisites for indirect assignment of Office 365 groups to Azure Active Directory user accounts	156
Assigning Exchange Online Office 365 groups to departments, cost centers, and locations	157
Assigning Exchange Online Office 365 groups to business roles	158
Adding Exchange Online Office 365 groups to system roles	159
Adding Exchange Online Office 365 groups to the IT Shop	160
Anwendungsrolle für Produkteigner ermittelt und Adding Exchange Online Office 365 groups automatically to the IT Shop	162
Assigning Exchange Online Office 365 groups directly to Azure Active Directory user accounts	164
Assigning Azure Active Directory user accounts directly to Exchange Online Office 365 groups	164
Exchange Online Office 365 group inheritance based on categories	165
Assigning extended properties to Exchange Online Office 365 groups	166
Deleting Exchange Online Office 365 groups	167
Exchange Online dynamic distribution groups	168
Editing main data of Exchange Online dynamic distribution groups	168
Main data for Exchange Online dynamic distribution groups	169
Customizing receive restrictions for Exchange Online dynamic distribution groups	171
Customizing send permissions for Exchange Online dynamic distribution groups	172
Specifying moderators for Exchange Online dynamic distribution groups	172
Adding Exchange Online mail-enabled distribution groups to Exchange Online dynamic distribution groups	173

Deleting Exchange Online dynamic distribution groups	174
Exchange Online mail-enabled public folders	175
Displaying information about Exchange Online mail-enabled public folders	175
Assigning Exchange Online mail-enabled distribution groups to Exchange Online mail-enabled public folders	176
Reports about Exchange Online objects	178
Appendix: Configuration parameters for managing an Exchange Online environment	180
Appendix: Default project template for Exchange Online	182
Appendix: Editing Exchange Online system objects	183
Appendix: Exchange Online connector settings	185
About us	187
Contacting us	187
Technical support resources	187
Index	188

About this guide

The *One Identity Manager Administration Guide for Connecting to Exchange Online* describes how you set up synchronization of Exchange Online with One Identity Manager. The guide explains how to use One Identity Manager to manage the mailboxes, email users, mail contacts, mail-enabled distribution groups, and Office 365 groups of your Exchange Online environment.

This guide is intended for end users, system administrators, consultants, analysts, and any other IT professionals using the product.

NOTE: This guide describes One Identity Manager functionality available to the default user. It is possible that not all the functions described here are available to you. This depends on your system configuration and permissions.

Available documentation

You can access One Identity Manager documentation in the Manager and in the Designer by selecting the **Help > Search** menu item. The online version of One Identity Manager documentation is available in the Support portal under [Technical Documentation](#). You will find videos with additional information at www.YouTube.com/OneIdentity.

Managing Exchange Online environments

The key aspects of administering an Exchange Online system with One Identity Manager are local mapping of mailboxes, mail users, mail contacts, mail-enabled distribution groups, and Office 365 groups from a cloud environment.

The system information for the Exchange Online structure is loaded into the One Identity Manager database during data synchronization. It is only possible to customize certain system information in One Identity Manager due to the complex dependencies and far reaching effects of changes.

For more information about the Exchange Online structure, see the *Exchange Online documentation* from Microsoft.


NOTE: The Exchange Online module must be installed as a prerequisite for managing One Identity Manager in Exchange Online Module. For more information about installing, see the *One Identity Manager Installation Guide*.

Architecture overview

To access Exchange Online organizational data, the Exchange Online connector is installed on a synchronization server. The synchronization server ensures data is compared between the One Identity Manager database and Exchange Online. The Exchange Online connector is part of the Exchange Online Module and responsible for communicating with the Microsoft Office 365 subscriptions of Exchange Online in the cloud. The Exchange Online PowerShell V2 module is used to access Exchange Online data.

To access the data in an Exchange Online organization, the Azure Active Directory target system containing the Exchange Online organization must be synchronized.

Figure 1: The synchronization architecture



One Identity Manager users for managing Exchange Online

The following users are used for setting up and administration of Exchange Online.

Table 1: Users

User	Tasks
Target system administrators	<p>Target system administrators must be assigned to the Target systems Administrators application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none">• Administer application roles for individual target system types.• Specify the target system manager.• Set up other application roles for target system managers if required.• Specify which application roles for target system managers are mutually exclusive.• Authorize other employees to be target system

User	Tasks
	<p>administrators.</p> <ul style="list-style-type: none"> Do not assume any administrative tasks within the target system.
Target system managers	<p>Target system managers must be assigned to the Target systems Exchange Online application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> Assume administrative tasks for the target system. Create, change, or delete target system objects. Edit password policies for the target system. Prepare groups to add to the IT Shop. Can add employees who have another identity than the Primary identity. Configure synchronization in the Synchronization Editor and define the mapping for comparing target systems and One Identity Manager. Edit the synchronization's target system types and outstanding objects. Authorize other employees within their area of responsibility as target system managers and create child application roles if required.
One Identity Manager administrators	<p>One Identity Manager administrator and administrative system users Administrative system users are not added to application roles.</p> <p>One Identity Manager administrators:</p> <ul style="list-style-type: none"> Create customized permissions groups for application roles for role-based login to administration tools in the Designer as required. Create system users and permissions groups for non role-based login to administration tools in the Designer as required. Enable or disable additional configuration parameters in the Designer as required. Create custom processes in the Designer as required. Create and configure schedules as required. Create and configure password policies as required.

Configuration parameters for managing Exchange Online environments

Use configuration parameters to configure the behavior of the system's basic settings. One Identity Manager provides default settings for different configuration parameters. Check the configuration parameters and modify them as necessary to suit your requirements.

Configuration parameters are defined in the One Identity Manager modules. Each One Identity Manager module can also install configuration parameters. In the Designer, you can find an overview of all configuration parameters in the **Base data > General > Configuration parameters** category.

For more information, see [Configuration parameters for managing an Exchange Online environment](#) on page 180.

Synchronizing an Exchange Online environment

The One Identity Manager Service is responsible for synchronizing data between the One Identity Manager database and Exchange Online.

This section explains how to:

- Set up synchronization to import initial data from Exchange Online Organization to the One Identity Manager database.
- Adjust a synchronization configuration
- Start and deactivate the synchronization.
- Analyze synchronization results.

TIP: Before you set up synchronization with an Exchange Online organization, familiarize yourself with the Synchronization Editor. For more information about this tool, see the *One Identity Manager Target System Synchronization Reference Guide*.

Detailed information about this topic

- [Setting up Exchange Online synchronization](#) on page 15
- [Customizing the synchronization configuration](#) on page 31
- [Running synchronization](#) on page 43
- [Tasks following synchronization](#) on page 47
- [Troubleshooting](#) on page 50
- [Ignoring data error in synchronization](#) on page 51
- [Editing Exchange Online system objects](#) on page 183

Setting up Exchange Online synchronization

The Synchronization Editor provides a project template that can be used to set up Exchange Online synchronization. You use these project templates to create synchronization projects with which you import the data from an Exchange Online organization into your One Identity Manager database. In addition, the required processes are created that are used for the provisioning of changes to target system objects from the One Identity Manager database into the target system.

Prerequisites for synchronizing Exchange Online are:

- The Azure Active Directory tenant is declared in One Identity Manager.
- Synchronization of the Azure Active Directory system is carried out regularly.

For more information about synchronizing an Azure Active Directory tenant, see the *One Identity Manager Administration Guide for Connecting to Azure Active Directory*.

To load Exchange Online objects into the One Identity Manager database for the first time

1. Prepare a user account in the Azure Active Directory tenant with sufficient permissions for synchronization.
2. One Identity Manager parts for managing Exchange Online systems are available if the **TargetSystem | AzureAD | ExchangeOnline** configuration parameter is set.
 - In the Designer, check if the configuration parameter is set. Otherwise, set the configuration parameter and compile the database.

NOTE: If you disable the configuration parameter at a later date, model components and scripts that are not longer required, are disabled. SQL procedures and triggers are still carried out. For more information about the behavior of preprocessor relevant configuration parameters and conditional compiling, see the *One Identity Manager Configuration Guide*.
 - Other configuration parameters are installed when the module is installed. Check the configuration parameters and modify them as necessary to suit your requirements.
3. Install and configure a synchronization server and declare the server as a Job server in One Identity Manager.
4. Create a synchronization project with the Synchronization Editor.

Detailed information about this topic

- [Users and permissions for synchronizing with Exchange Online](#) on page 16
- [Setting up the Exchange Online synchronization server](#) on page 18
- [Preparing the administrative workstation for access to Exchange Online](#) on page 22
- [Preparing a remote connection server for access to Exchange Online](#) on page 22

- [Creating a synchronization project for initial synchronization of an Exchange Online environment](#) on page 23
- [Exchange Online synchronization features](#) on page 28
- [Customizing the synchronization configuration](#) on page 31
- [Configuration parameters for managing an Exchange Online environment](#) on page 180
- [Default project template for Exchange Online](#) on page 182

Users and permissions for synchronizing with Exchange Online

The following users are involved in synchronizing One Identity Manager with Exchange Online.

Table 2: Users for synchronization

User	Permissions
User account for accessing Exchange Online	<p>To synchronize Exchange Online, provide a user account with at least the following permissions.</p> <ul style="list-style-type: none"> • Member of the Recipient Management Exchange Online role group • Member of the Records Management Exchange Online role group • Member of the View-Only Organization Management Exchange Online role group • Member of the Security Group Creation and Membership Exchange Online role group <p>NOTE: Create a new role group in Exchange Online. Assign the role and the user account to this role group.</p> <ul style="list-style-type: none"> • Member of the Groups administrator Azure Active Directory administrator role <p>NOTE: The user account used to access Exchange Online must not use multifactor authentication to allow automated logins in a user context.</p> <p>Use the Exchange Admin Center to assign Exchange Online role groups to user accounts. Use the Azure Active Directory Admin Center to assign the Azure Active Directory administrator role to the user account. For example, you can reach the Admin Center over https://admin.microsoft.com/. For more information on managing permissions in Exchange Online and in Azure Active Directory, see the <i>Microsoft documentation</i>.</p>
One Identity	The user account for the One Identity Manager Service requires user permissions to carry out operations at file level (adding and editing

User	Permissions
Manager Service user account	<p>directories and files).</p> <p>The user account must belong to the Domain users group.</p> <p>The user account must have the Login as a service extended user permissions.</p> <p>The user account requires permissions for the internal web service.</p> <p>NOTE: If the One Identity Manager Service runs under the network service (NT Authority\NetworkService), you can grant permissions for the internal web service with the following command line call:</p> <pre>netsh http add urlacl url=http://<IP address>:<port number>/ user="NT AUTHORITY\NETWORKSERVICE"</pre> <p>The user account needs full access to the One Identity Manager Service installation directory in order to automatically update One Identity Manager.</p> <p>In the default installation, One Identity Manager is installed under:</p> <ul style="list-style-type: none"> • %ProgramFiles(x86)%\One Identity (on 32-bit operating systems) • %ProgramFiles%\One Identity (on 64-bit operating systems)
User for accessing the One Identity Manager database	<p>The Synchronization default system user is provided to run synchronization using an application server.</p>

Installing the Exchange Online PowerShell V2 module

The Exchange Online connector uses Exchange Online PowerShell V2 module to access data in Exchange Online.

- The Exchange Online PowerShell V2 module must be installed on the synchronization server.
- If Exchange Online is accessed directly from the workstation on which Synchronization Editor is installed, the Exchange Online PowerShell V2 module must also be installed on this workstation.
- If direct access from the workstation to Exchange Online is not possible, you can set up a remote connection. The Exchange Online PowerShell V2 module must be installed on the remote connection server.

For more information about prerequisites and installing the Exchange Online PowerShell V2 module, see the [Exchange Online PowerShell documentation from Microsoft](#).

Related topics

- [Setting up the Exchange Online synchronization server](#) on page 18
- [Preparing the administrative workstation for access to Exchange Online](#) on page 22
- [Preparing a remote connection server for access to Exchange Online](#) on page 22

Setting up the Exchange Online synchronization server

All One Identity Manager Service actions are run against the target system environment on the synchronization server. Data entries required for synchronization and administration with the One Identity Manager database are processed by the synchronization server.

The One Identity Manager Service with the Exchange Online connector must be installed on the synchronization server.

IMPORTANT: The Exchange Online connector uses Exchange Online PowerShell V2 module to access data in Exchange Online. The Exchange Online PowerShell V2 module must be installed on the synchronization server.

Detailed information about this topic

- [System requirements for the Exchange Online synchronization server](#) on page 18
- [Installing the Exchange Online PowerShell V2 module](#) on page 17
- [Installing One Identity Manager Service with an Exchange Online connector](#) on page 19

System requirements for the Exchange Online synchronization server

To set up synchronization with an Exchange Online environment, a server has to be available that has the following software installed on it:

- Windows operating system
The following versions are supported:
 - Windows Server 2022
 - Windows Server 2019
 - Windows Server 2016
 - Windows Server 2012 R2
 - Windows Server 2012
- Microsoft .NET Framework Version 4.7.2 or later

| **NOTE:** Take the target system manufacturer's recommendations into account.

- Windows PowerShell 5.1 or later
- Exchange Online PowerShell V2 module

Related topics

- [Installing the Exchange Online PowerShell V2 module](#) on page 17
- [Installing One Identity Manager Service with an Exchange Online connector](#) on page 19

Installing One Identity Manager Service with an Exchange Online connector

The One Identity Manager Service must be installed on the synchronization server with the Exchange Online connector. The synchronization server must be declared as a Job server in One Identity Manager.

Table 3: Properties of the Job server

Property	Value
Server function	Exchange Online connector
Machine role	Server Job server Exchange Online

NOTE: If several target system environments of the same type are synchronized under the same synchronization server, it is recommended that you set up a Job server for each target system for performance reasons. This avoids unnecessary swapping of connections to target systems because a Job server only has to process tasks of the same type (re-use of existing connections).

Use the One Identity Manager Service to install the Server Installer. The program runs the following steps:

- Sets up a Job server.
- Specifies machine roles and server function for the Job server.
- Remotely installs One Identity Manager Service components corresponding to the machine roles.
- Configures the One Identity Manager Service.
- Starts the One Identity Manager Service.

NOTE: The program performs a remote installation of the One Identity Manager Service. Local installation of the service is not possible with this program.

To remotely install the One Identity Manager Service, you must have an administrative workstation on which the One Identity Manager components are installed. For detailed

information about installing a workstation, see the *One Identity Manager Installation Guide*.

NOTE: To generate processes for the Job server, you need the provider, connection parameters, and the authentication data. By default, this information is determined from the database connection data. If the Job server runs through an application server, you must configure extra connection data in the Designer. For detailed information about setting up Job servers, see the *One Identity Manager Configuration Guide*.

To remotely install and configure One Identity Manager Service on a server

1. Start the Server Installer program on your administrative workstation.
2. On the **Database connection** page, enter the valid connection credentials for the One Identity Manager database.
3. On the **Server properties** page, specify the server on which you want to install the One Identity Manager Service.
 - a. Select a Job server from the **Server** menu.

- OR -

To create a new Job server, click **Add**.

- b. Enter the following data for the Job server.
 - **Server:** Name of the Job server.
 - **Queue:** Name of the queue to handle the process steps. Each Job server within the network must have a unique queue identifier. The process steps are requested by the Job queue using this exact queue name. The queue identifier is entered in the One Identity Manager Service configuration file.
 - **Full server name:** Full server name in accordance with DNS syntax.

Syntax:

<Name of servers>.<Fully qualified domain name>

NOTE: You can use the **Extended** option to make changes to other properties for the Job server. You can also edit the properties later with the Designer.

4. On the **Machine roles** page, select **Exchange Online**.
5. On the **Server functions** page, select **Exchange Online connector (via Windows PowerShell)**.
6. On the **Service Settings** page, enter the connection data and check the One Identity Manager Service configuration.

NOTE: The initial service configuration is predefined. If further changes need to be made to the configuration, you can do this later with the Designer. For detailed information about configuring the service, see the *One Identity Manager Configuration Guide*.

- For a direct connection to the database:
 1. Select **Process collection > sqlprovider**.
 2. Click the **Connection parameter** entry, then click the **Edit** button.
 3. Enter the connection data for the One Identity Manager database.
 - For a connection to the application server:
 1. Select **Process collection**, click the **Insert** button and select **AppServerJobProvider**.
 2. Click the **Connection parameter** entry, then click the **Edit** button.
 3. Enter the connection data for the application server.
 4. Click the **Authentication data** entry and click the **Edit** button.
 5. Select the authentication module. Depending on the authentication module, other data may be required, such as user and password. For detailed information about One Identity Manager authentication modules, see the *One Identity Manager Authorization and Authentication Guide*.
7. To configure remote installations, click **Next**.
 8. Confirm the security prompt with **Yes**.
 9. On the **Select installation source** page, select the directory with the install files. Change the directory if necessary.
 10. If the database is encrypted, on the **Select private key file** page, select the file with the private key.
 11. On the **Service access** page, enter the service's installation data.
 - **Computer:** Enter the name or IP address of the server that the service is installed and started on.
 - **Service account:** Enter the details of the user account that the One Identity Manager Service is running under. Enter the user account, the user account's password and password confirmation.

The service is installed using the user account with which you are logged in to the administrative workstation. If you want to use another user account for installing the service, you can enter it in the advanced options. You can also change the One Identity Manager Service details, such as the installation directory, name, display name, and the One Identity Manager Service description, using the advanced options.
 12. Click **Next** to start installing the service.

Installation of the service occurs automatically and may take some time.
 13. Click **Finish** on the last page of the Server Installer.
- NOTE:** In a default installation, the service is entered in the server's service management with the name **One Identity Manager Service**.

Preparing the administrative workstation for access to Exchange Online

To configure synchronization with Exchange Online in the Synchronization Editor, One Identity Manager must load the data directly from Exchange Online. If the Exchange Online is accessed directly from the work station on which the Synchronization Editor is installed, the following software must also be installed on this workstation:

- Windows PowerShell Version 5.1 or later
- Exchange Online PowerShell V2 module

If direct access from the workstation to Exchange Online is not possible, you can set up a remote connection.

Related topics

- [Installing the Exchange Online PowerShell V2 module](#) on page 17
- [Users and permissions for synchronizing with Exchange Online](#) on page 16
- [Preparing a remote connection server for access to Exchange Online](#) on page 22

Preparing a remote connection server for access to Exchange Online

To configure synchronization with a target system, One Identity Manager must load the data from the target system. One Identity Manager communicates directly with the target system to do this. Sometimes direct access from the workstation, on which the Synchronization Editor is installed, is not possible. For example, because of the firewall configuration or the workstation does not fulfill the necessary hardware and software requirements. If direct access is not possible from the workstation, you can set up a remote connection.

The remote connection server and the workstation must be in the same Active Directory domain.

Remote connection server configuration:

- One Identity Manager Service is started
- **RemoteConnectPlugin** is installed
- Windows PowerShell version 5.1 or above is installed
- Exchange Online PowerShell V2 module is installed.
- Exchange Online connector is installed

The remote connection server must be declared as a Job server in One Identity Manager. The Job server name is required.

TIP: The remote connection server requires the same configuration as the synchronization server (with regard to the installed software and entitlements). Use the synchronization as remote connection server at the same time, by simply installing the **RemoteConnectPlugin** as well.

For more detailed information about setting up a remote connection, see the *One Identity Manager Target System Synchronization Reference Guide*.

Related topics

- [Setting up the Exchange Online synchronization server](#) on page 18
- [Installing the Exchange Online PowerShell V2 module](#) on page 17
- [Installing One Identity Manager Service with an Exchange Online connector](#) on page 19
- [Users and permissions for synchronizing with Exchange Online](#) on page 16
- [Preparing the administrative workstation for access to Exchange Online](#) on page 22

Creating a synchronization project for initial synchronization of an Exchange Online environment

Use the Synchronization Editor to configure synchronization between the One Identity Manager database and Exchange Online environment. The following describes the steps for initial configuration of a synchronization project. For more information about setting up synchronization, see the *One Identity Manager Target System Synchronization Reference Guide*

After the initial configuration, you can customize and configure workflows within the synchronization project. Use the workflow wizard in the Synchronization Editor for this. The Synchronization Editor also provides different configuration options for a synchronization project.

IMPORTANT: Each Exchange Online environment should have its own synchronization project.

IMPORTANT: It must be possible to reach Exchange Online servers by DNS query for successful authentication. If the DNS cannot be resolved, the target system connection is refused.

NOTE: When setting up the synchronization, note the recommendations described under [Exchange Online synchronization features](#) on page 28.

Prerequisites for setting up a synchronization project

- The Azure Active Directory tenant is declared in One Identity Manager.
- Synchronization of the Azure Active Directory system is carried out regularly.

Related topics

- [Information required for Exchange Online synchronization projects](#) on page 24
- [Creating an initial synchronization project for Exchange Online](#) on page 25
- [Exchange Online synchronization features](#) on page 28
- [Customizing the synchronization configuration](#) on page 31
- [Default project template for Exchange Online](#) on page 182
- [Exchange Online connector settings](#) on page 185

Information required for Exchange Online synchronization projects

Have the following information available for setting up a synchronization project.

Table 4: Information required to set up a synchronization project

Data	Explanation
User account and password for logging in	<p>User account and password for logging in to Exchange Online.</p> <p>Example:</p> <pre><user>@<domain.com></pre> <p><user name of the synchronization user>@yourorganization.onmicrosoft.com</p> <p>Make a user account available with sufficient permissions. For more information, see Users and permissions for synchronizing with Exchange Online on page 16.</p>
Synchronization server for Exchange Online	<p>All One Identity Manager Service actions are run against the target system environment on the synchronization server. Data entries required for synchronization and administration with the One Identity Manager database are processed by the synchronization server.</p> <p>The One Identity Manager Service with the Exchange Online connector must be installed on the synchronization server.</p> <p>The synchronization server must be declared as a Job server in One Identity Manager. Use the following properties when you set up the Job server.</p> <ul style="list-style-type: none">• Server function: Exchange Online connector• Machine role: Server Jobserver Exchange Online <p>For more information, see Setting up the Exchange Online synchronization server on page 18.</p>
One Identity	<ul style="list-style-type: none">• Database server

Data	Explanation
Manager database connection data	<ul style="list-style-type: none"> • Database name • SQL Server login and password • Specifies whether integrated Windows authentication is used <p>Use of the integrated Windows authentication is not recommended. If you decide to use it anyway, ensure that your environment supports Windows authentication.</p>
Remote connection server	For more information, see Preparing a remote connection server for access to Exchange Online on page 22.

Creating an initial synchronization project for Exchange Online

IMPORTANT: Each Exchange Online environment should have its own synchronization project.

NOTE: The following sequence describes how to configure a synchronization project if the Synchronization Editor is both:

- Run in default mode
- Started from the Launchpad

If you run the project wizard in expert mode or directly from the Synchronization Editor, additional configuration settings can be made. Follow the project wizard instructions through these steps.

To set up initial synchronization project for Exchange Online

1. Start the Launchpad and log in on the One Identity Manager database.

NOTE: If synchronization is run by an application server, connect the database through the application server.

2. Select the **Target system type Exchange Online** entry and click **Start**.

This starts the Synchronization Editor's project wizard.

3. On the **System access** page, specify how One Identity Manager can access the target system.

- If access is possible from the workstation on which you started the Synchronization Editor, do not change any settings.
- If access is not possible from the workstation on which you started the Synchronization Editor, you can set up a remote connection.

Enable the **Connect using remote connection server** option and select the server to be used for the connection under **Job server**.

4. On the **Deployment** page, select the cloud deployment where your Exchange Online environment will run.
5. On the **Connection parameters** page, enter the login data for connecting to Exchange Online.

- **User name:** Enter the fully qualified name (FQDN) of the user account for logging in.

Example:

<user>@<domain.com>

sync.user@yourorganisation.onmicrosoft.com

- **Password:** Enter the pass word of the user account.

Click ☒ to test the connection parameter.

6. On the last page of the system connection wizard, click **Finish** to return to the project wizard.
7. On the **One Identity Manager Connection** tab, test the data for connecting to the One Identity Manager database. The data is loaded from the connected database. Reenter the password.

NOTE:

- If you use an unencrypted One Identity Manager database and have not yet saved any synchronization projects to the database, you need to enter all connection data again.
 - This page is not shown if a synchronization project already exists.
8. The wizard loads the target system schema. This may take a few minutes depending on the type of target system access and the size of the target system.
 9. On the **Restrict target system access** page, specify how system access should work. You have the following options:


Table 5: Specify target system access

Option	Meaning
	Specifies that a synchronization workflow is only to be set up for the initial loading of the target system into the One Identity Manager database.
	The synchronization workflow has the following characteristics:
	<ul style="list-style-type: none"> • Synchronization is in the direction of One Identity Manager. • Processing methods in the synchronization steps are only defined for synchronization in the direction of One Identity Manager.

Option	Meaning
Read/write access to target system. Provisioning available.	<p>Specifies whether a provisioning workflow is set up in addition to the synchronization workflow for the initial loading of the target system.</p> <p>The provisioning workflow displays the following characteristics:</p> <ul style="list-style-type: none"> • Synchronization is in the direction of the Target system. • Processing methods are only defined in the synchronization steps for synchronization in the direction of the Target system. • Synchronization steps are only created for such schema classes whose schema types have write access.

10. On the **Synchronization server** page, select the synchronization server to run the synchronization.

If the synchronization server is not declared as a Job server in the One Identity Manager database yet, you can add a new Job server.

- Click  to add a new Job server.
- Enter a name for the Job server and the full server name conforming to DNS syntax.
- Click **OK**.

The synchronization server is declared as Job server for the target system in the One Identity Manager database.

- NOTE:** After you save the synchronization project, ensure that this server is set up as a synchronization server.

11. To close the project wizard, click **Finish**.

This creates and allocates a default schedule for regular synchronization. Enable the schedule for regular synchronization.

This sets up, saves and immediately activates the synchronization project.

NOTE:

- If enabled, a consistency check is carried out. If errors occur, a message appears. You can decide whether the synchronization project can remain activated or not.

Check the errors before you use the synchronization project. To do this, in the **General** view on the Synchronization Editor's start page, click **Verify project**.

- If you do not want the synchronization project to be activated immediately, disable the **Activate and save the new synchronization project automatically option**. In this case, save the synchronization project manually before closing the Synchronization Editor.
- The connection data for the target system is saved in a variable set and can be modified in the Synchronization Editor in the **Configuration > Variables** category.

Related topics

- [Users and permissions for synchronizing with Exchange Online](#) on page 16
- [Information required for Exchange Online synchronization projects](#) on page 24
- [Setting up the Exchange Online synchronization server](#) on page 18
- [Configuring the synchronization log](#) on page 30
- [Customizing the synchronization configuration](#) on page 31
- [Running synchronization](#) on page 43
- [Tasks following synchronization](#) on page 47
- [Default project template for Exchange Online](#) on page 182
- [Exchange Online connector settings](#) on page 185

Exchange Online synchronization features

There are a number of features for synchronizing Exchange Online environments, which are described here.

Dependency resolution

By default, automatic dependency resolution for synchronization steps is not set in the synchronization workflow. This reduces the number of calls required to Exchange Online. This can lead to unresolved references during synchronization that are handled in the maintenance phase at the end of synchronization.

Multiple organizations are not supported

Due to the dynamic number of used login accounts, variable sets cannot be used to parametrize the connection. For this reason, creating more base objects in one synchronization project is not supported.

Changing mailbox types in the Exchange Online portal

The default project template for Exchange Online support the conversion of mailbox types as follows:

- Shared mailbox to user mailbox
- User mailbox to share mailbox
- Equipment mailbox to room mailbox
- Room mailbox to equipment mailbox

NOTE: In performing an unsupported change, for example, a room mailbox to a shared mailbox, the synchronization will mark the room mailbox as "missing" and fail to create the shared mailbox due to naming violations. This scenario can only be resolved manually.

NOTE: One Identity Manager does not support handling of mailbox types.

Synchronization of mailbox statistic data

Synchronization of mailbox statistic data is done in its own synchronization step. Loading this information from Exchange Online is potentially very time consuming. Therefore, it make sense to create a separate workflow that includes a synchronization step for loading this data. You can run this workflow at longer intervals than the workflow without usage data.

The following usage information is synchronized:

Schema property in the Target System	Description
AssociatedItemCount	Number of elements associated with this mailbox.
DeletedItemCount	Number of deleted elements.
DumpsterMessagesPerFolderCountReceiveQuota	Maximum number of messages allowed in a folder in the Recoverable items folder.
DumpsterMessagesPerFolderCountWarningQuota	Number of items a folder in the Recoverable items folder can contain before a warning is sent to the user.
ItemCount	Number of messages in a mailbox (for example, email, calendar, or contacts) that are visible to the user.
LastLoggedInUserAccount	Name of the last logged on user.
LastLogOffTime	Last log off time
LastLogonTime	Last log on time
StorageLimitStatus	Information about the current storage state with respect to the specified limits.
TotalDeletedItemSize	Size of items in the Recoverable Items mailbox.

Schema property in the Target System	Description
TotalItemSize	Size of items in mailbox in KB.

NOTE: The mailbox usage information is only available for users or shared mailboxes.

Number of external slots for the Job server configuration

Since the number of concurrent connections for Exchange Online is limited to three, you should use a dedicated Job server with a reduced number of external slots (not more than two). You will get an error message if too many connections are open at the same time.

You can set the number of connections for each connection parameter set and customize the connector definition. For more information, see [Advanced settings for the Exchange Online connector](#) on page 35.

Configuring the synchronization log

All the information, tips, warnings, and errors that occur during synchronization are recorded in the synchronization log. You can configure the type of information to record separately for each system connection.

To configure the content of the synchronization log

1. To configure the synchronization log for target system connection, select the **Configuration > Target system** category in the Synchronization Editor.
- OR -
To configure the synchronization log for the database connection, select the **Configuration > One Identity Manager connection** category in the Synchronization Editor.
2. Select the **General** view and click **Configure**.
3. Select the **Synchronization log** view and set **Create synchronization log**.
4. Enable the data to be logged.

NOTE: Some content generates a particularly large volume of log data. The synchronization log should only contain data required for error analysis and other analyzes.

5. Click **OK**.

Synchronization logs are stored for a fixed length of time.

To modify the retention period for synchronization logs

- In the Designer, enable the **DPR | Journal | LifeTime** configuration parameter and enter the maximum retention period.

Related topics

- [Displaying synchronization results](#) on page 45

Customizing the synchronization configuration

Having used the Synchronization Editor to set up a synchronization project for initial synchronization of Exchange Online, you can use the synchronization project to load Exchange Online objects into the One Identity Manager database. When you manage mailboxes, mail users, mail contacts, mail-enabled distribution groups, and Office 365 groups with One Identity Manager, modifications are provisioned in the Exchange Online system.

You must customize the synchronization configuration in order to compare the One Identity Manager database with the Exchange Online regularly and to synchronize changes.

- To use One Identity Manager as the primary system during synchronization, create a workflow with synchronization in the direction of the **Target system**.
- You can use variables to create generally applicable synchronization configurations that contain the necessary information about the synchronization objects when synchronization starts. Variables can be implemented in base objects, schema classes, or processing method, for example.
- To specify which Exchange Online objects and database objects are included in synchronization, edit the scope of the target system connection and the One Identity Manager database connection. To prevent data inconsistencies, define the same scope in both systems. If no scope is defined, all objects will be synchronized.
- Update the schema in the synchronization project if the One Identity Manager schema or target system schema has changed. Then you can add the changes to the mapping.

For more information about configuring synchronization, see the *.One Identity Manager Target System Synchronization Reference Guide*

Detailed information about this topic

- [Exchange Online synchronization features](#) on page 28
- [How to configure Exchange Online synchronization](#) on page 32
- [Changing system connection settings of Exchange Online](#) on page 32
- [Updating schemas](#) on page 37
- [Speeding up Exchange Online synchronization with revision filtering](#) on page 38
- [Configuring the provisioning of memberships](#) on page 40

- [Configuring single object synchronization](#) on page 41
- [Accelerating provisioning and single object synchronization](#) on page 42

How to configure Exchange Online synchronization

The synchronization project for initial synchronization provides a workflow for initial loading of target system objects (initial synchronization) and one for provisioning object modifications from the One Identity Manager database to the target system (provisioning). To use One Identity Manager as the primary system during synchronization, you also require a workflow with synchronization in the direction of the **Target system**.

To create a synchronization configuration for synchronizing Exchange Online

1. In the Synchronization Editor, open the synchronization project.
2. Check whether the existing mappings can be used to synchronize into the target system. Create new maps if required.
3. Create a new workflow with the workflow wizard.
This creates a workflow with **Target system** as its direction of synchronization.
4. Create a new start up configuration. Use the new workflow to do this.
5. Save the changes.
6. Run a consistency check.

Changing system connection settings of Exchange Online

When you set up synchronization for the first time, the system connection properties are set to default values that you can modify. There are two ways to do this:

- a. Specify a specialized variable set and change the values of the affected variables.
The default values remain untouched in the default variable set. The variables can be reset to the default values at any time. (Recommended action).
- b. Edit the target system connection with the system connection wizard and change the effected values.
The system connection wizard supplies additional explanations of the settings. The default values can only be restored under particular conditions.

Detailed information about this topic





- [Editing connection parameters in the variable set](#) on page 33
- [Editing target system connection properties](#) on page 34
- [Advanced settings for the Exchange Online connector](#) on page 35
- [Exchange Online connector settings](#) on page 185

Editing connection parameters in the variable set

The connection parameters were saved as variables in the default variable set when synchronization was set up. You can change the values in these variables to suit your requirements and assign the variable set to a start up configuration and a base object. This means that you always have the option to use default values from the default variable set.

NOTE: To guarantee data consistency in the connected target system, ensure that the start-up configuration for synchronization and the base object for provisioning use the same variable set.

To customize connection parameters in a specialized variable set

1. In the Synchronization Editor, open the synchronization project.
2. Select the **Configuration > Target system** category.
3. Open the **Connection parameters** view.
Some connection parameters can be converted to variables here. For other parameters, variables are already created.
4. Select a parameter and click **Convert**.
5. Select the **Configuration > Variables** category.
All specialized variable sets are shown in the lower part of the document view.
6. Select a specialized variable set or click on  in the variable set view's toolbar.
 - To rename the variable set, select the variable set and click the variable set view in the toolbar . Enter a name for the variable set.
7. Select the previously added variable and enter a new value.
8. Select the **Configuration > Start up configurations** category.
9. Select a start up configuration and click **Edit**.
10. Select the **General** tab.
11. Select the specialized variable set in the **Variable set** menu.
12. Select the **Configuration > Base objects** category.
13. Select the base object and click .
- OR -
To add a new base object, click .

14. Select the specialized variable set in the **Variable set** menu.
15. Save the changes.

For detailed information about using variables and variable sets, or restoring default values and adding base objects, see the *One Identity Manager Target System Synchronization Reference Guide*.

Related topics

- [Editing target system connection properties](#) on page 34

Editing target system connection properties

You can also use the system connection wizard to change the connection parameters. If variables are defined for the settings, the changes are transferred to the active variable set.

NOTE: In the following circumstances, the default values cannot be restored:

- The connection parameters are not defined as variables.
- The default variable set is selected as an active variable set.

In both these cases, the system connection wizard overwrites the default values. They cannot be restored at a later time.

To edit connection parameters using the system connection wizard

1. In the Synchronization Editor, open the synchronization project.
2. In the toolbar, select the active variable set to be used for the connection to the target system.
NOTE: If the default variable set is selected, the default values are overwritten and cannot be restored at a later time.
3. Select the **Configuration > Target system** category.
4. Click **Edit connection**.
This starts the system connection wizard.
5. Follow the system connection wizard instructions and change the relevant properties.
6. Save the changes.

Related topics

- [Editing connection parameters in the variable set](#) on page 33

Advanced settings for the Exchange Online connector

You can specify whether you want to set advanced options in the Synchronization Editor project wizard on the **Connect Exchange Online** page. These settings allow you to change the following options for communicating with Exchange Online:

- The number of concurrent connections per connection parameter set
- The definition of Windows PowerShell commands

Number of concurrent connections per connection parameter set

IMPORTANT: You should only make changes to this option with the help of support desk staff. Changes to this setting will have wide ranging effects on synchronization and must be made carefully.

Use this option to set the number of concurrent connections for each connection parameter set or for each user account for synchronization. The setting specifies how many concurrent connections will be created for each user account. The default value is **2**. Exchange Online currently allows **3** connections per user account on the server side.


When the Exchange Online connector creates the connection, it creates one Windows PowerShell session per connection parameter set regardless of the number of queries that follow. Further connections are created on demand, for example, when loading multiple objects during the synchronization.

The maximum number of sessions established to Exchange Online can be calculated with the following formula:

Maximum number of Windows PowerShell sessions = Number of parameter sets * Value of concurrent connections per connection parameter set

The minimum number of sessions established to Exchange Online is the same as the number of connection parameter sets.

Figure 2: Determining sessions



To change the number of concurrent connections

1. In the Synchronization Editor, open the synchronization project.
2. Select the **Configuration > Target system** category.
 1. Click **Edit connection**.

This starts the system connection wizard.
3. On the system connection wizard's start page, enable **Show advanced options**.
4. On the Advanced settings page, in the **concurrent connections per connection parameter set** input field, enter a value between **1** and **3**.
5. Follow the system connection wizard further instructions.
6. Save the changes.

Customizing the connection definition




You can use this setting to adjust the definition used by the connector in order to convert inputs and outputs between the Exchange Online Cmdlets and the schema of the

Synchronization Engine.

IMPORTANT: You should only make changes to the connector definition with the help of support desk staff. Changes to this setting will have wide ranging effects on synchronization and must be made carefully.

NOTE: A customized connection definition is not overwritten by default and must be made with careful consideration.

To customize the connector definition

1. In the Synchronization Editor, open the synchronization project.
2. Select the **Configuration > Target system** category.
3. Click **Edit connection**.
This starts the system connection wizard.
4. Enable **Show advanced options** on the system connection wizard's start page.
5. Customize the connector definition as required on the **Advanced options** page.
 - a. Select **Customize connector definition**.
 - b. Edit the definition according to the instructions given by the support desk staff.
You take the following action:
 - Choose  to load the definition from a file.
 - Use  to test the definition for errors.
 - Choose  to display the differences to the standard version.
6. Follow the system connection wizard further instructions.
7. Save the changes.

Updating schemas

All the schema data (schema types and schema properties) of the target system schema and the One Identity Manager schema are available when you are editing a synchronization project. Only a part of this data is really needed for configuring synchronization. If a synchronization project is finished, the schema is compressed to remove unnecessary data from the synchronization project. This can speed up the loading of the synchronization project. Deleted schema data can be added to the synchronization configuration again at a later point.

If the target system schema or the One Identity Manager schema has changed, these changes must also be added to the synchronization configuration. Then the changes can be added to the schema property mapping.

To include schema data that have been deleted through compression and schema modifications in the synchronization project, update each schema in the synchronization project. This may be necessary if:

- A schema was changed by:
 - Changes to a target system schema
 - Customizations to the One Identity Manager schema
 - A One Identity Manager update migration
- A schema in the synchronization project was shrunk by:
 - Enabling the synchronization project
 - Saving the synchronization project for the first time
 - Compressing a schema

To update a system connection schema

1. In the Synchronization Editor, open the synchronization project.
2. Select the **Configuration > Target system** category.
- OR -
Select the **Configuration > One Identity Manager connection** category.
3. Select the **General** view and click **Update schema**.
4. Confirm the security prompt with **Yes**.
This reloads the schema data.

To edit a mapping

1. In the Synchronization Editor, open the synchronization project.
2. Select the **Mappings** category.
3. Select a mapping in the navigation view.
Opens the Mapping Editor. For more information about mappings, see the *One Identity Manager Target System Synchronization Reference Guide*.

NOTE: The synchronization is deactivated if the schema of an activated synchronization project is updated. Reactivate the synchronization project to synchronize.

Speeding up Exchange Online synchronization with revision filtering

When you start synchronization, all synchronization objects are loaded. Some of these objects have not be modified since the last synchronization and, therefore, must not be processed. Synchronization is accelerated by only loading those object pairs that have changed since the last synchronization. One Identity Manager uses revision filtering to accelerate synchronization.

Exchange Online supports revision filtering for the schema types Mailbox, MailUser, MailContact, MailPublicFolder, DistributionGroup, DynamicDistributionGroup, and UnifiedGroup.

You can configure the change time stamp for revision filtering using the following connection parameters in the synchronization project.

- **Use local server time for the revision:** If the value is **true**, the local server time of the server is used for revision filtering. (default) This makes it unnecessary to load target system object for determining the revision. If the value is **false**, the change time stamp of the underlying Azure Active Directory objects are used for revision filtering.

Variable: CP_UseLocalServerTimeAsRevision

- **Max. time difference (local/remote) in minutes:** Defines the maximum time difference in minutes between the synchronization server and the Exchange Online server. The default value is 60 minutes. If the time difference is more than 60 minutes, alter the value.

Variable: CP_LocalServerRevisionMaxDifferenceInMinutes

The time resulting from the local server time and the maximum time difference is saved as the revision number in the One Identity Manager database (DPRRevisionStore table, Value column). If the local server time is used, the revision number is calculated from the time at which the object was changed.

This value is used as a comparison for revision filtering when the same workflow is synchronized the next time. The next time synchronization is run, only those objects that have been changed since this date are loaded. This avoids unnecessary updating of objects that have not changed since the last synchronization.

The revision is found at start of synchronization. Objects modified by synchronization are loaded and checked by the next synchronization. This means that the second synchronization after initial synchronization is not significantly faster.

Revision filtering can be applied to workflows and start up configuration.

To permit revision filtering on a workflow

- In the Synchronization Editor, open the synchronization project.
- Edit the workflow properties. Select the **Use revision filter** item from **Revision filtering** menu.

To permit revision filtering for a start up configuration

- In the Synchronization Editor, open the synchronization project.
- Edit the start up configuration properties. Select the **Use revision filter** item from the **Revision filtering** menu.

For more detailed information about revision filtering, adjusting connections parameters and editing variables, see the *One Identity Manager Target System Synchronization Reference Guide*.

Related topics

- [Changing system connection settings of Exchange Online](#) on page 32

Configuring the provisioning of memberships

Memberships, such as user accounts in groups, are saved in assignment tables in the One Identity Manager database. During provisioning of modified memberships, changes made in the target system may be overwritten. This behavior can occur under the following conditions:

- Memberships are saved as an object property in list form in the target system.
Example: List of mailboxes in the `AcceptMessagesOnlyFrom` property of an Exchange Online mailbox (Mailbox)
- Memberships can be modified in either of the connected systems.
- A provisioning workflow and provisioning processes are set up.

If one membership in One Identity Manager changes, by default, the complete list of members is transferred to the target system. Therefore, memberships that were previously added to the target system are removed in the process and previously deleted memberships are added again.

To prevent this, provisioning can be configured such that only the modified membership is provisioned in the target system. The corresponding behavior is configured separately for each assignment table.

To allow separate provisioning of memberships

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Target system types** category.
2. In the result list, select the **Exchange Online** target system type.
3. Select the **Configure tables for publishing** task.
4. Select the assignment tables that you want to set up for single provisioning. Multi-select is possible.
5. Click **Merge mode**.


NOTE:

- This option can only be enabled for assignment tables that have a base table with a `XDateSubItem` column.
- Assignment tables that are grouped together in a virtual schema property in the mapping must be marked identically.

6. Save the changes.

For each assignment table labeled like this, the changes made in One Identity Manager are saved in a separate table. Therefore, only newly added and deleted assignments are processed. During modification provisioning, the members list in the target system is compared to the entries in this table. This means that only modified memberships are provisioned and not the entire members list.

NOTE: The complete members list is updated by synchronization. During this process, objects with changes but incomplete provisioning are not handled. These objects are logged in the synchronization log.

You can restrict single provisioning of memberships with a condition. Once merge mode has been disabled for a table, the condition is deleted. Tables that have had the condition deleted or edited are marked with the following icon: . You can restore the original condition at any time.

To restore the original condition

1. Select the auxiliary table for which you want to restore the condition.
2. Right-click on the selected row and select the **Restore original values** context menu item.
3. Save the changes.

NOTE: To create the reference to the added or deleted assignments in the condition, use the *i* table alias.

Example of a condition on the O3EUnifiedGroupAcceptRcpt assignment table:

```
exists (select top 1 1 from O3EUnifiedGroup g
        where g.UID_O3EUnifiedGroup = i.UID_O3EUnifiedGroup
        and <limiting condition>)
```

For more information about provisioning memberships, see the *One Identity Manager Target System Synchronization Reference Guide*.

Configuring single object synchronization

Changes made to individual objects in the target system can be immediately applied in the One Identity Manager database without having to start a full synchronization of the target system environment. Individual objects can only be synchronized if the object is already present in the One Identity Manager database. The changes are applied to the mapped object properties. If a membership list belongs to one of these properties, the entries in the assignment table will also be updated. If the object is no longer present in the target system, then it is deleted from the One Identity Manager database.

Prerequisites

- A synchronization step exists that can import the changes to the changed object into One Identity Manager.
- The path to the base object of the synchronization is defined for the table that contains the changed object.

Single object synchronization is fully configured for synchronization projects created using the default project template. If you want to incorporate custom tables into this type of synchronization project, you must configure single object synchronization for these tables. For more information about this, see the *One Identity Manager Target System Synchronization Reference Guide*.

To define the path to the base object for synchronization for a custom table

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Target system types** category.
2. In the result list, select the **Exchange Online** target system type.
3. Select the **Assign synchronization tables** task.
4. In the **Add assignments** pane, assign the custom table for which you want to use single object synchronization.
5. Save the changes.
6. Select the **Configure tables for publishing** task.
7. Select the custom table and enter the **Root object path**.
Enter the path to the base object in the ObjectWalker notation of the VI.DB.
Example: FK(UID_AADOrganization).XObjectKey
8. Save the changes.

Related topics

- [Synchronizing single objects](#) on page 46
- [Post-processing outstanding objects](#) on page 47

Accelerating provisioning and single object synchronization

To smooth out spikes in data traffic, handling of processes for provisioning and single object synchronization can be distributed over several Job servers. This will also accelerate these processes.

NOTE: You should not implement load balancing for provisioning or single object synchronization on a permanent basis. Parallel processing of objects might result in dependencies not being resolved because referenced objects from another Job server have not been completely processed.

Once load balancing is no longer required, ensure that the synchronization server runs the provisioning processes and single object synchronization.

To configure load balancing

1. Configure the server and declare it as a Job server in One Identity Manager.
 - Job servers that share processing must have the **No process assignment** option enabled.
 - Assign the **Exchange Online connector** server function to the Job server.

All Job servers must access the same Azure Active Directory tenant as the synchronization server for the respective base object.

2. In the Synchronization Editor, assign a custom server function to the base object.

This server function is used to identify all the Job servers being used for load balancing.

If there is no custom server function for the base object, create a new one.

For more information about editing base objects, see the *One Identity Manager Target System Synchronization Reference Guide*.

3. In the Manager, assign this server function to all the Job servers that will be processing provisioning and single object synchronization for the base object.

Only select those Job servers that have the same configuration as the base object's synchronization server.

Once all the processes have been handled, the synchronization server takes over provisioning and single object synchronization again.

To use the synchronization server without load balancing.

- In the Synchronization Editor, remove the server function from the base object.

For detailed information about load balancing, see the *One Identity Manager Target System Synchronization Reference Guide*.

Detailed information about this topic

- [Job server for Exchange Online-specific process handling](#) on page 76

Running synchronization

Synchronization is started using scheduled process plans. It is possible to start synchronization manually in the Synchronization Editor. You can simulate synchronization beforehand to estimate synchronization results and discover errors in the synchronization configuration. If synchronization stopped unexpectedly, you must reset the start information to be able to restart synchronization.

If you want to specify the order in which target systems are synchronized, use the start up sequence to run synchronization. In a start up sequence, you can combine start up configurations from different synchronization projects and specify the order in which they are run. For more information about start up sequences, see the *One Identity Manager Target System Synchronization Reference Guide*.

Detailed information about this topic

- [Starting synchronization](#) on page 44
- [Deactivating synchronization](#) on page 45

- [Displaying synchronization results](#) on page 45
- [Synchronizing single objects](#) on page 46

Starting synchronization

When you set up the initial synchronization project using the Launchpad, a default schedule for regular synchronization is created and assigned. Activate this schedule to synchronize on a regular basis.

To synchronize on a regular basis

1. In the Synchronization Editor, open the synchronization project.
2. Select the **Configuration > Start up configurations** category.
3. Select a start up configuration in the document view and click **Edit schedule**.
4. Edit the schedule properties.
5. To enable the schedule, click **Activate**.
6. Click **OK**.

You can also start synchronization manually if there is no active schedule.

To start initial synchronization manually

1. In the Synchronization Editor, open the synchronization project.
2. Select the **Configuration > Start up configurations** category.
3. Select a start up configuration in the document view and click **Run**.
4. Confirm the security prompt with **Yes**.

IMPORTANT: As long as a synchronization process is running, you must not start another synchronization process for the same target system. This especially applies, if the same synchronization objects would be processed.

- If another synchronization process is started with the same start up configuration, the process is stopped and is assigned **Frozen** status. An error message is written to the One Identity Manager Service log file.
 - Ensure that start up configurations that are used in start up sequences are not started individually at the same time. Assign start up sequences and start up configurations different schedules.
- Starting another synchronization process with different start up configuration that addresses same target system may lead to synchronization errors or loss of data. Specify One Identity Manager behavior in this case, in the start up configuration.
 - Use the schedule to ensure that the start up configurations are run in sequence.
 - Group start up configurations with the same start up behavior.

Deactivating synchronization

Regular synchronization cannot be started until the synchronization project and the schedule are active.

To prevent regular synchronization

1. In the Synchronization Editor, open the synchronization project.
2. Select the start up configuration and deactivate the configured schedule.

Now you can only start synchronization manually.

An activated synchronization project can only be edited to a limited extent. The schema in the synchronization project must be updated if schema modifications are required. The synchronization project is deactivated in this case and can be edited again.

Furthermore, the synchronization project must be deactivated if synchronization should not be started by any means (not even manually).

To deactivate the synchronization project

1. In the Synchronization Editor, open the synchronization project.
2. Select the **General** view on the home page.
3. Click **Deactivate project**.

Related topics

- [Creating a synchronization project for initial synchronization of an Exchange Online environment](#) on page 23

Displaying synchronization results


Synchronization results are summarized in the synchronization log. You can specify the extent of the synchronization log for each system connection individually. One Identity Manager provides several reports in which the synchronization results are organized under different criteria.

To display a synchronization log

1. In the Synchronization Editor, open the synchronization project.
2. Select the **Logs** category.
3. Click ► in the navigation view toolbar.
Logs for all completed synchronization runs are displayed in the navigation view.
4. Select a log by double-clicking it.

An analysis of the synchronization is shown as a report. You can save the report.

To display a provisioning log

1. In the Synchronization Editor, open the synchronization project.
2. Select the **Logs** category.
3. Click  in the navigation view toolbar.
Logs for all completed provisioning processes are displayed in the navigation view.
4. Select a log by double-clicking it.
An analysis of the provisioning is shown as a report. You can save the report.

The log is marked in color in the navigation view. This mark shows you the status of the synchronization/provisioning.

TIP: The logs are also displayed in the Manager under the **<target system> > synchronization log** category.

Synchronization logs are stored for a fixed length of time.

To modify the retention period for synchronization logs

- In the Designer, enable the **DPR | Journal | LifeTime** configuration parameter and enter the maximum retention period.

Synchronizing single objects

Individual objects can only be synchronized if the object is already present in the One Identity Manager database. The changes are applied to the mapped object properties. If a membership list belongs to one of these properties, the entries in the assignment table will also be updated.

NOTE: If the object is no longer present in the target system, then it is deleted from the One Identity Manager database.

To synchronize a single object

1. In the Manager, select the **Azure Active Directory** category.
2. Select the object type in the navigation view.
3. In the result list, select the object that you want to synchronize.
4. Select the **Synchronize this object** task.

A process for reading this object is entered in the job queue.

Features of synchronizing memberships

If you synchronize changes in an object's member list, run single object synchronization on the assignment's root object. The base table of an assignment contains an XDateSubItem column containing information about the last change to the memberships.

Example:

Base object for assigning receive restrictions for Exchange Online email users and mail-enabled distribution groups is the distribution group.

In the target system, mail acceptance for a mail-enabled distribution group was allowed for an email user. To synchronize this assignment, in the Manager, select this distribution group and run single object synchronization. In the process, all of the distribution group's assignments are synchronized.

The email user must already exist as an object in the One Identity Manager database for the assignment to be made.

Detailed information about this topic

- [Configuring single object synchronization](#) on page 41

Tasks following synchronization

After the synchronization of data from the target system into the One Identity Manager database, rework may be necessary. Check the following tasks:

- [Post-processing outstanding objects](#) on page 47
- [Adding custom tables to the target system synchronization](#) on page 49
- [Managing Exchange Online mail users and Exchange Online mail contacts through account definitions](#) on page 50

Post-processing outstanding objects

Objects, which do not exist in the target system, can be marked as outstanding in One Identity Manager by synchronizing. This prevents objects being deleted because of an incorrect data situation or an incorrect synchronization configuration.

Outstanding objects:

- Cannot be edited in One Identity Manager.
- Are ignored by subsequent synchronizations.
- Are ignored by inheritance calculations.

This means, all memberships and assignments remain intact until the outstanding objects have been processed.

Start target system synchronization to do this.

To post-process outstanding objects

1. In the Manager, select the **Azure Active Directory > Target system synchronization: Exchange Online** category.

The navigation view lists all the synchronization tables assigned to the **Exchange Online** target system type.

2. On the **Target system synchronization** form, in the **Table / object** column, open the node of the table for which you want to post-process outstanding objects.

All objects that are marked as outstanding are shown. The **Last log entry** and **Last method run** columns display the time at which the last entry was made in the synchronization log and which processing method was run. The **No log available** entry can mean the following:



- The synchronization log has already been deleted.
- OR -
- An assignment from a member list has been deleted from the target system.
The base object of the assignment was updated during the synchronization. A corresponding entry appears in the synchronization log. The entry in the assignment table is marked as outstanding, but there is no entry in the synchronization log.
- An object that contains a member list has been deleted from the target system.
During synchronization, the object and all corresponding entries in the assignment tables are marked as outstanding. However, an entry in the synchronization log appears only for the deleted object.


TIP:

To display object properties of an outstanding object

1. Select the object on the target system synchronization form.
 2. Open the context menu and click **Show object**.
3. Select the objects you want to rework. Multi-select is possible.
 4. Click on one of the following icons in the form toolbar to run the respective method.

Table 6: Methods for handling outstanding objects

Icon	Method	Description
	Delete	The object is immediately deleted from the One Identity Manager database. Deferred deletion is not taken into account. Indirect memberships cannot be deleted.
	Publish	The object is added to the target system. The Outstanding label is removed from the object. This runs a target system specific process that triggers the provisioning process for the object.

Icon	Method	Description
		Prerequisites: <ul style="list-style-type: none"> • The table containing the object can be published. • The target system connector has write access to the target system.
	Reset	The Outstanding label is removed for the object.

5. Confirm the security prompt with **Yes**.

NOTE: By default, the selected objects are processed in parallel, which speeds up the selected method. If an error occurs during processing, the action is stopped and all changes are discarded.

Bulk processing of objects must be disabled if errors are to be localized, which means the objects are processed sequentially. Failed objects are named in the error message. All changes that were made up until the error occurred are saved.

To disable bulk processing

- Disable the  icon in the form's toolbar.

NOTE: The target system connector must have write access to the target system in order to publish outstanding objects that are being post-processed. That means, the **Connection is read-only** option must not be set for the target system connection.

Adding custom tables to the target system synchronization

You must customize your target system synchronization to synchronize custom tables.

To add custom tables to target system synchronization

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Target system types** category.
2. In the result list, select the **Exchange Online** target system type.
3. Select the **Assign synchronization tables** task.
4. In the Add assignments pane, assign **custom** tables to the outstanding objects you want to handle.
5. Save the changes.
6. Select the **Configure tables for publishing** task.
7. Select the custom tables that contain the outstanding objects that can be published in the target system and set the **Publishable** option.
8. Save the changes.

Related topics

- [Post-processing outstanding objects](#) on page 47

Managing Exchange Online mail users and Exchange Online mail contacts through account definitions

In the default installation, after synchronizing, employees are automatically created for Exchange Online mail users and Exchange Online mail contacts. If an account definition for the Exchange Online organization is not known at the time of synchronization, mail users and mail contacts are linked to the employees. However, account definitions are not assigned. The mail users and mail contacts are therefore in a **Linked** state.

To manage mail users and mail contacts through account definitions, assign an account definition and a manage level.

To manage Exchange Online mail users and mail contacts through account definitions

1. Create an account definition.
2. Assign an account definition to the Azure Active Directory tenant.
3. Assign the account definition and manage level to user accounts in **linked** status.
 - a. In the Manager, select the **Azure Active Directory > Mail users > Linked but not configured > <Azure Active Directory tenant>** category.
- OR -
In the Manager, select the **Azure Active Directory > Mail contacts > Linked but not configured > <Azure Active Directory tenant>** category.
 - b. Select the **Assign account definition to linked accounts** task.

Related topics

- [Account definitions for Exchange Online mail users and Exchange Online mail contacts](#) on page 54
- [Assigning account definitions to Azure Active Directory tenants](#) on page 71

Troubleshooting

Synchronization Editor helps you to analyze and eliminate synchronization errors.

- Simulating synchronization

The simulation allows you to estimate the result of synchronization. This means you can, for example, recognize potential errors in the synchronization configuration.

- Analyzing synchronization

You can generate the synchronization analysis report for analyzing problems which occur during synchronization, for example, insufficient performance.

- Logging messages

One Identity Manager offers different options for logging errors. These include the synchronization log, the log file for One Identity Manager Service, the logging of messages with NLOG, and similar.

- Reset start information

If synchronization stopped unexpectedly, for example, because a server was not available, the start information must be reset manually. Only then can the synchronization be restarted.

For more information about these topics, see the *One Identity Manager Target System Synchronization Reference Guide*.

Related topics

- [Displaying synchronization results](#) on page 45

Ignoring data error in synchronization

By default, objects with incorrect data are not synchronized. These objects can be synchronized once the data has been corrected. In certain situations, however, it might be necessary to synchronize objects like these and ignore the data properties that have errors. This synchronization behavior can be configured in One Identity Manager.

To ignoring data errors during synchronization in One Identity Manager

1. In the Synchronization Editor, open the synchronization project.
2. Select the **Configuration > One Identity Manager connection** category.
3. In the **General** view, click **Edit connection**.

This starts the system connection wizard.

4. On the **Additional options** page, enable **Try to ignore data errors**.

This option is only effective if **Continue on error** is set in the synchronization workflow.

Default columns, such as primary keys, UID columns, or mandatory input columns cannot be ignored.

5. Save the changes.

IMPORTANT: If this option is set, One Identity Manager tries to ignore commit errors that could be related to data errors in a single column. This causes the data changed in the affected column to be discarded and the object is subsequently saved again. This effects performance and leads to loss of data.

Only set this option in the exceptional circumstance of not being able to correct the data before synchronization.

Basic data for managing an Exchange Online environment

To manage an Exchange Online environment in One Identity Manager, the following basic data is relevant.

- Account definitions

One Identity Manager has account definitions for automatically allocating user accounts to employees. You can create account definitions for every target system. If an employee does not yet have a user account in a target system, a new user account is created. This is done by assigning account definitions to an employee.

For more information, see [Account definitions for Exchange Online mail users and Exchange Online mail contacts](#) on page 54.

- Password policies

One Identity Manager provides you with support for creating complex password policies, for example, for system user passwords, the employees' central password as well as passwords for individual target systems. Password policies apply not only when the user enters a password but also when random passwords are generated.

Predefined password policies are supplied with the default installation that you can use or customize if required. You can also define your own password policies.

Azure Active Directory configuration settings are used for implementing password policies. For more information, see the *One Identity Manager Administration Guide for Connecting to Azure Active Directory*.

- Initial password for new mail users.

You can issue an initial password for mail users in the following ways: Enter a password or use a random generated initial password when you create a mail user.

Azure Active Directory configuration settings are used for generating random passwords for new mail users. For more information, see the *One Identity Manager Administration Guide for Connecting to Azure Active Directory*.

- Email notifications about credentials

When a new mail user is created, the login data are sent to a specified recipient. In this case, two messages are sent with the user name and the initial password. Mail templates are used to generate the messages.

Azure Active Directory configuration settings are used for sending login credentials. For more information, see the *One Identity Manager Administration Guide for Connecting to Azure Active Directory*.

- Target system types

Target system types are required for configuring target system comparisons. Tables with outstanding objects are maintained with the target system types and settings are configured for provisioning memberships and single objects synchronization. Target system types also map objects in the Unified Namespace.

For more information, see [Post-processing outstanding objects](#) on page 47.

- Target system managers

A default application role exists for the target system manager in One Identity Manager. Assign the employees who have permission to edit all Exchange Online objects in One Identity Manager to this application role.

Define additional application roles if you want to limit the permissions for target system managers to individual tenants with Exchange Online. The application roles must be added under the default application role.

For more information, see [Target system managers for Exchange Online](#) on page 74.

- Servers

Servers must be informed of your server functionality in order to handle Exchange Online-specific processes in One Identity Manager. For example, the synchronization server.

For more information, see [Job server for Exchange Online-specific process handling](#) on page 76.

Account definitions for Exchange Online mail users and Exchange Online mail contacts

NOTE: Exchange Online user mailboxes are create or deleted respectively by assigning and removing licenses through Azure Active Directory subscriptions. For more information, see the *One Identity Manager Administration Guide for Connecting to Azure Active Directory*.

One Identity Manager has account definitions for automatically allocating mail users and mail contacts to employees. You can create account definitions for every target system. If an employee does not yet have a mail user or mail contact in a target system, a new mail user or mail contact is created by assigning the account definition to an employee.

For detailed information about account definitions, see the *One Identity Manager Target System Base Module Administration Guide*.

The following steps are required to implement an account definition:


- Creating account definitions
- Configuring manage levels
- Creating the formatting rules for IT operating data
- Collecting IT operating data
- Assigning account definitions to employees and target systems

Detailed information about this topic

- [Creating account definitions](#) on page 55
- [Editing account definitions](#) on page 56
- [Main data for account definitions](#) on page 56
- [Editing manage levels](#) on page 58
- [Creating manage levels](#) on page 59
- [Assigning manage levels to account definitions](#) on page 60
- [Main data for manage levels](#) on page 60
- [Creating mapping rules for IT operating data](#) on page 61
- [Entering IT operating data](#) on page 62
- [Modify IT operating data](#) on page 63
- [Assigning account definitions to employees](#) on page 64
- [Assigning account definitions to Azure Active Directory tenants](#) on page 71
- [Deleting account definitions](#) on page 71

Creating account definitions

To create a new account definition

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Click  in the result list.
3. On the main data form, enter the main data of the account definition.
4. Save the changes.

Detailed information about this topic

- [Main data for account definitions](#) on page 56
- [Editing account definitions](#) on page 56
- [Assigning manage levels to account definitions](#) on page 60

Editing account definitions

To edit an account definition

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Change main data** task.
4. Enter the account definition's main data.
5. Save the changes.

Related topics

- [Main data for account definitions](#) on page 56
- [Creating account definitions](#) on page 55
- [Assigning manage levels to account definitions](#) on page 60

Main data for account definitions

Enter the following data for an account definition:

Table 7: Main data for an account definition

Property	Description
Account definition	Account definition name.
User account table	Table in the One Identity Manager schema that maps mail users or mail contacts. For Exchange Online mail users, select O3EMailUser . For Exchange Online mail contacts, select O3EMailContact .
Target system	Target system to which the account definition applies.
Required account definition	Specifies the required account definition. Define the dependencies between account definitions. When this account definition is requested or assigned, the required account definition

Property	Description
	is assigned automatically. Leave empty for Exchange Online.
Description	Text field for additional explanation.
Manage level (initial)	Manage level to use by default when you add new mail users or mail contacts.
Risk index	Value for evaluating the risk of assigning the account definition to employees. Set a value in the range 0 to 1 . This input field is only visible if the QER CalculateRiskIndex configuration parameter is set. For detailed information, see the <i>One Identity Manager Risk Assessment Administration Guide</i> .
Service item	Service item through which you can request the account definition resource in the IT Shop. Assign an existing service item or add a new one.
IT Shop	Specifies whether the account definition can be requested through the IT Shop. The account definition can be requested by an employee through the Web Portal and distributed using a defined approval process. The resource can also be assigned directly to employees and roles outside the IT Shop.
Only for use in IT Shop	Specifies whether the account definition can only be requested through the IT Shop. The account definition can be requested by an employee through the Web Portal and distributed using a defined approval process. The account definition cannot be directly assigned to roles outside the IT Shop.
Automatic assignment to employees	Specifies whether the account definition is automatically assigned to all internal employees. To automatically assign the account definition to all internal employee, use the Enable automatic assignment to employees . The account definition is assigned to every employee that is not marked as external. Once a new internal employee is created, they automatically obtain this account definition. To automatically remove the account definition assignment from all employees, use the Disable automatic assignment to employees . The account definition cannot be reassigned to employees from this point on. Existing account definition assignments remain intact.
Retain account definition if permanently disabled	Specifies the account definition assignment to permanently deactivated employees.

Property	Description
	<p>Option set: The account definition assignment remains in effect. The mail user or mail contact remains intact.</p> <p>Option not set (default): The account definition assignment is not in effect. The associated mail user or the associated mail contact is disabled.</p>
Retain account definition if temporarily disabled	<p>Specifies the account definition assignment to temporarily deactivated employees.</p> <p>Option set: The account definition assignment remains in effect. The mail user or mail contact remains intact.</p> <p>Option not set (default): The account definition assignment is not in effect. The associated mail user or the associated mail contact is disabled.</p>
Retain account definition on deferred deletion	<p>Specifies the account definition assignment on deferred deletion of employees.</p> <p>Option set: The account definition assignment remains in effect. The mail user or mail contact remains intact.</p> <p>Option not set (default): The account definition assignment is not in effect. The associated mail user or the associated mail contact is disabled.</p>
Retain account definition on security risk	<p>Specifies the account definition assignment to employees posing a security risk.</p> <p>Option set: The account definition assignment remains in effect. The email user or mail contact remains intact.</p> <p>Option not set (default): The account definition assignment is not in effect. The associated mail user or the associated mail contact is disabled.</p>
Resource type	Resource type for grouping account definitions.
Spare field 01 - spare field 10	Additional company-specific information. Use the Designer to customize display names, formats, and templates for the input fields.

Editing manage levels

One Identity Manager supplies a default configuration for the **Unmanaged** and **Full managed** manage levels. You can define other manage levels depending on your requirements.

IMPORTANT: In the Designer, extend the templates by adding the procedure for the additional manage levels. For detailed information about templates, see the *One Identity Manager Configuration Guide*.

For more information about manage levels, see the *One Identity Manager Target System Base Module Administration Guide*.

To edit a manage level

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Manage levels** category.
2. Select the manage level in the result list.
3. Select the **Change main data** task.
4. Edit the manage level's main data.
5. Save the changes.

Related topics

- [Main data for manage levels](#) on page 60
- [Creating manage levels](#) on page 59
- [Assigning manage levels to account definitions](#) on page 60


Creating manage levels

One Identity Manager supplies a default configuration for the **Unmanaged** and **Full managed** manage levels. You can define other manage levels depending on your requirements.

IMPORTANT: In the Designer, extend the templates by adding the procedure for the additional manage levels. For detailed information about templates, see the *One Identity Manager Configuration Guide*.

For more information about manage levels, see the *One Identity Manager Target System Base Module Administration Guide*.

To create a manage level

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Manage levels** category.
2. Click  in the result list.
3. On the main data form, edit the main data of the manage level.
4. Save the changes.

Related topics

- [Main data for manage levels](#) on page 60
- [Editing manage levels](#) on page 58
- [Assigning manage levels to account definitions](#) on page 60

Assigning manage levels to account definitions


IMPORTANT: The **Unmanaged** manage level is assigned automatically when you create an account definition and it cannot be removed.

To assign manage levels to an account definition

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Assign manage level** task.
4. In the **Add assignments** pane, assign the manage level.

TIP: In the **Remove assignments** pane, you can remove assigned manage levels.

To remove an assignment

- Select the manage level and double-click .
5. Save the changes.

Main data for manage levels

Enter the following data for a manage level.

Table 8: Main data for manage levels

Property	Description
Manage level	Name of the manage level.
Description	Text field for additional explanation.
IT operating data overwrites	Specifies whether user account data formatted from IT operating data is automatically updated. Permitted values are: <ul style="list-style-type: none">• Never: Data is not updated. (Default)• Always: Data is always updated.• Only initially: Data is only determined at the start.
Retain groups if temporarily disabled	Specifies whether user accounts of temporarily deactivated retain their group memberships.
Lock user accounts if temporarily disabled	Specifies whether user accounts of temporarily deactivated employees are locked.
Retain groups if	Specifies whether user accounts of permanently deactivated

Property	Description
permanently disabled	employees retain group memberships.
Lock user accounts if permanently disabled	Specifies whether user accounts of permanently deactivated employees are locked.
Retain groups on deferred deletion	Specifies whether user accounts of employees marked for deletion retain their group memberships.
Lock user accounts if deletion is deferred	Specifies whether user accounts of employees marked for deletion are locked.
Retain groups on security risk	Specifies whether user accounts of employees posing a security risk retain their group memberships.
Lock user accounts if security is at risk	Specifies whether user accounts of employees posing a security risk are locked.
Retain groups if user account disabled	Specifies whether disabled user accounts retain their group memberships.

Creating mapping rules for IT operating data

An account definition specifies which rules are used to form the IT operating data and which default values will be used if no IT operating data can be found through the employee's primary roles.

The following IT operating data is used in the One Identity Manager default configuration for automatically creating user accounts for an employee in the target system and modifying them.

- Groups can be inherited

To create a mapping rule for IT operating data

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Edit IT operating data mapping** task.
4. Click **Add** and enter the following information:
 - **Column:** User account property for which the value is set. In the menu, you can select the columns that use the TSB_ITDataFromOrg script in their template. For more information about this, see the *One Identity Manager Target System Base Module Administration Guide*.
 - **Source:** Specifies which roles to use in order to find the user account properties. You have the following options:

- Primary department
- Primary location
- Primary cost center
- Primary business roles

NOTE: The business role can only be used if the Business Roles Module is available.

- Empty

If you select a role, you must specify a default value and set the **Always use default value** option.

- **Default value:** Default value of the property for an employee's user account if the value is not determined dynamically from the IT operating data.
- **Always use default value:** Specifies whether the user account property is always set with the default value. IT operating data is not determined dynamically from a role.
- **Notify when applying the default:** Specifies whether an email is sent to a specific mailbox when the default value is used. The **Employee - new user account with default properties created** mail template is used.

5. Save the changes.

Related topics

- [Entering IT operating data](#) on page 62

Entering IT operating data

To create user accounts with the **Full managed** manage level, the required IT operating data must be determined. The operating data required to automatically supply an employee with IT resources is shown in the business roles, departments, locations, or cost centers. An employee is assigned a primary business role, primary location, primary department, or primary cost center. The necessary IT operating data is ascertained from these assignments and used in creating the user accounts. Default values are used if valid IT operating data cannot be found over the primary roles.

You can also specify IT operating data directly for a specific account definition.

Example:

Normally, each employee in department A obtains a default user account in the client A. In addition, certain employees in department A obtain administrative user accounts in the client A.

Create an account definition A for the default user account of the tenant A and an account definition B for the administrative user account of tenant A. In the IT operating data mapping rule for the account definitions A and B, specify the **Department** property in order to determine the valid IT operating data.

Specify the effective IT operating data of department A for the tenant A. This IT operating data is used for standard user accounts. In addition, for department A, specify the effective IT operating data of account definition B. This IT operating data is used for administrative user accounts.

To define IT operating data

1. In the Manager, select the role in the **Organizations** or **Business roles** category.
2. Select the **Edit IT operating data** task.
3. Click **Add** and enter the following data.
 - **Effects on:** Specify an IT operating data application scope. The IT operating data can be used for a target system or a defined account definition.

To specify an application scope

- a. Click ➔ next to the field.
 - b. Under **Table**, select the table that maps the target system for select the TSBAccountDef table or an account definition.
 - c. Select the specific target system or account definition under **Effects on**.
 - d. Click **OK**.
- **Column:** Select the user account property for which the value is set.

In the menu, you can select the columns that use the TSB_ITDataFromOrg script in their template. For more information about this, see the *One Identity Manager Target System Base Module Administration Guide*.
 - **Value:** Enter a fixed value to assign to the user account's property.
4. Save the changes.

Related topics

- [Creating mapping rules for IT operating data](#) on page 61

Modify IT operating data

If IT operating data changes, you must transfer the changes to the existing user accounts. To do this, templates must be rerun on the affected columns. Before you can run the templates, you can check what effect a change to the IT operating data has on the existing user accounts. You can decide whether the change is transferred to the One Identity Manager database in the case of each affected column in each affected database.

Prerequisites

- The IT operating data of a department, a cost center, a business role, or a location have been changed.
 - OR -
- The default values in the IT operating data template were modified for an account definition.

NOTE: If the assignment of an employee to a primary department, cost center, to a primary business role or to a primary location changes, the templates are automatically run.

To run the template

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Run templates** task.

This displays a list of all user accounts that were created with the selected account definition and whose properties were changed by modifying the IT operating data. That means:

- **Old value:** Value of the object property before changing the IT operating data.
 - **New value:** Value of the object property after changing the IT operating data.
 - **Selection:** Specifies whether the new value is copied to the user account.
4. Mark all the object properties in the **selection** column that will be given the new value.
 5. Click **Apply**.

The templates are applied to all selected user accounts and properties.

Assigning account definitions to employees

Account definitions are assigned to company employees.

Indirect assignment is the default method for assigning account definitions to employees. Account definitions are assigned to departments, cost centers, locations, or roles. The employees are categorized into these departments, cost centers, locations, or roles depending on their function in the company and thus obtain their account definitions. To react quickly to special requests, you can assign individual account definitions directly to employees.

You can automatically assign special account definitions to all company employees. It is possible to assign account definitions to the IT Shop as requestable products. Department managers can then request user accounts from the Web Portal for their staff. It is also possible to add account definitions to system roles. These system roles can be assigned to employees through hierarchical roles or added directly to the IT Shop as products.

In the One Identity Manager default installation, the processes are checked at the start to see if the employee already has a user account in the target system that has an account definition. If no user account exists, a new user account is created with the account definition's default manage level.

NOTE: If a user account already exists and is disabled, then it is re-enabled. In this case, you must change the user account manage level afterward.

NOTE: As long as an account definition for an employee is valid, the employee retains the user account that was created by it. If the account definition assignment is removed, the user account that was created from this account definition, is deleted.

Prerequisites for indirect assignment of account definitions to employees

- Assignment of employees and account definitions is permitted for role classes (departments, cost centers, locations, or business roles).

To configure assignments to roles of a role class

1. In the Manager, select role classes in the **Organizations > Basic configuration data > Role classes** category.
- OR -
In the Manager, select role classes in the **Business roles > Basic configuration data > Role classes** category.
2. Select the **Configure role assignments** task and configure the permitted assignments.
 - To generally allow an assignment, enable the **Assignments allowed** column.
 - To allow direct assignment, enable the **Direct assignments permitted** column.
3. Save the changes.

For detailed information about preparing role classes to be assigned, see the *One Identity Manager Identity Management Base Module Administration Guide*.

Detailed information about this topic

- [Assigning account definitions to departments, cost centers, and locations](#) on page 66
- [Assigning account definitions to business roles](#) on page 66
- [Assigning account definitions to all employees](#) on page 67
- [Assigning account definitions directly to employees](#) on page 68
- [Assigning account definitions to Azure Active Directory tenants](#) on page 71


Assigning account definitions to departments, cost centers, and locations

To add account definitions to hierarchical roles

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Assign organizations** task.
4. In the **Add assignments** pane, assign the organizations:
 - On the **Departments** tab, assign departments.
 - On the **Locations** tab, assign locations.
 - On the **Cost centers** tab, assign cost centers.

TIP: In the **Remove assignments** pane, you can remove assigned organizations.

To remove an assignment

- Select the organization and double-click .
5. Save the changes.

Related topics

- [Assigning account definitions to business roles](#) on page 66
- [Assigning account definitions to business roles](#) on page 66
- [Assigning account definitions directly to employees](#) on page 68

Assigning account definitions to business roles


NOTE: This function is only available if the Business Roles Module is installed.

To add account definitions to hierarchical roles

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Assign business roles** task.
4. In the **Add assignments** pane, select the role class and assign business roles.

TIP: In the **Remove assignments** pane, you can remove assigned business roles.

To remove an assignment

- Select the business role and double-click .
5. Save the changes.

Related topics

- [Assigning account definitions to departments, cost centers, and locations](#) on page 66
- [Assigning account definitions to all employees](#) on page 67
- [Assigning account definitions directly to employees](#) on page 68

Assigning account definitions to all employees

Use this task to assign the account definition to all internal employees. Employees that are marked as external do not obtain this account definition. Once a new internal employee is created, they automatically obtain this account definition. The assignment is calculated by the DBQueue Processor.

IMPORTANT: Only run this task if you can ensure that all current internal employees in the database and all pending newly added internal employees obtain a user account in this target system.

To assign an account definition to all employees

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Change main data** task.
4. Select the **Disable automatic assignment to employees** task.
5. Confirm the security prompt with **Yes**.
6. Save the changes.

NOTE: To automatically remove the account definition assignment from all employees, run the [DISABLE AUTOMATIC ASSIGNMENT TO EMPLOYEES](#) task. The account definition cannot be reassigned to employees from this point on. Existing assignments remain intact.

Related topics

- [Assigning account definitions to departments, cost centers, and locations](#) on page 66
- [Assigning account definitions to business roles](#) on page 66
- [Assigning account definitions directly to employees](#) on page 68


Assigning account definitions directly to employees

To assign an account definition directly to employees

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Assign to employees** task.
4. In the **Add assignments** pane, add employees.

TIP: In the **Remove assignments** pane, you can remove assigned employees.

To remove an assignment

- Select the employee and double-click .
5. Save the changes.

Related topics

- [Assigning account definitions to departments, cost centers, and locations](#) on page 66
- [Assigning account definitions to business roles](#) on page 66
- [Assigning account definitions to all employees](#) on page 67

Assigning account definitions to system roles

NOTE: This function is only available if the System Roles Module is installed.


Account definitions with the **Only use in IT Shop** option can only be assigned to system roles that also have this option set.

To add account definitions to a system role

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Assign system roles** task.
4. In the **Add assignments** pane, assign system roles.

TIP: In the **Remove assignments** pane, you can remove assigned system roles.

To remove an assignment

- Select the system role and double-click .
5. Save the changes.

Adding account definitions in the IT Shop

An account definition can be requested by shop customers when it is assigned to an IT Shop shelf. To ensure it can be requested, further prerequisites need to be guaranteed.

- The account definition must be labeled with the **IT Shop** option.
- The account definition must be assigned to a service item.

TIP: In the Web Portal, all products that can be requested are grouped together by service category. To make the account definition easier to find in the Web Portal, assign a service category to the service item.

- If the account definition is only assigned to employees using IT Shop assignments, you must also set the **Only for use in IT Shop** option. Direct assignment to hierarchical roles may not be possible.

NOTE: IT Shop administrators can assign account definitions to IT Shop shelves if login is role-based. Target system administrators are not authorized to add account definitions in the IT Shop.

To add an account definition to the IT Shop (role-based login)

1. In the Manager, select the **Entitlements > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Add to IT Shop** task.
4. In the **Add assignments** pane, assign the account definitions to the IT Shop shelves.
5. Save the changes.

To add an account definition to the IT Shop (non role-based login)

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Add to IT Shop** task.
4. In the **Add assignments** pane, assign the account definitions to the IT Shop shelves.
5. Save the changes.

To remove an account definition from individual IT Shop shelves (role-based login)

1. In the Manager, select the **Entitlements > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Add to IT Shop** task.

4. In the **Remove assignments** pane, remove the account definitions from the IT Shop shelves.
5. Save the changes.

To remove an account definition from individual IT Shop shelves (non role-based login)

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Add to IT Shop** task.
4. In the **Remove assignments** pane, remove the account definitions from the IT Shop shelves.
5. Save the changes.

To remove an account definition from all IT Shop shelves (role-based login)

1. In the Manager, select the **Entitlements > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Remove from all shelves (IT Shop)** task.
4. Confirm the security prompt with **Yes**.
5. Click **OK**.

The account definition is removed from all shelves by the One Identity Manager Service. At the same time, any requests and assignment requests with this account definition are canceled.

To remove an account definition from all IT Shop shelves (non role-based login)

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
2. Select an account definition in the result list.
3. Select the **Remove from all shelves (IT Shop)** task.
4. Confirm the security prompt with **Yes**.
5. Click **OK**.

The account definition is removed from all shelves by the One Identity Manager Service. At the same time, any requests and assignment requests with this account definition are canceled.

For detailed information about requesting company resources through the IT Shop, see the *One Identity Manager IT Shop Administration Guide*.

Related topics

- [Main data for account definitions](#) on page 56
- [Assigning account definitions to departments, cost centers, and locations](#) on page 66

- [Assigning account definitions to business roles](#) on page 66
- [Assigning account definitions directly to employees](#) on page 68
- [Assigning account definitions to system roles](#) on page 68

Assigning account definitions to Azure Active Directory tenants

The following prerequisites must be fulfilled if you implement automatic assignment of user accounts and employees resulting in administered user accounts (**Linked configured** state):

- The account definition is assigned to the target system.
- The account definition has the default manage level.

User accounts are only linked to the employee (**Linked** state) if no account definition is given. This is the case on initial synchronization, for example.

To assign the account definition to a target system

1. In the Manager, select the Azure Active Directory tenant in the **Azure Active Directory > Tenants** category.
2. Select the **Change main data** task.
3. From the **Account definition (initial)** menu, select the account definition for user accounts.
4. From the **Mail contact definition (initial)** menu, select the account definition for mail contacts.
5. From the **Mail user definition (initial)** menu, select the account definition for mail users.
6. Save the changes.

Related topics

- [Assigning account definitions to employees](#) on page 64

Deleting account definitions

You can delete account definitions if they are not assigned to target systems, employees, hierarchical roles or any other account definitions.

To delete an account definition

1. Remove automatic assignments of the account definition from all employees.
 - a. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
 - b. Select an account definition in the result list.
 - c. Select the **Change main data** task.
 - d. Select the **Disable automatic assignment to employees** task.
 - e. Confirm the security prompt with **Yes**.
 - f. Save the changes.
2. Remove direct assignments of the account definition to employees.
 - a. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
 - b. Select an account definition in the result list.
 - c. Select the **Assign to employees** task.
 - d. In the **Remove assignments** pane, remove employees.
 - e. Save the changes.
3. Remove the account definition's assignments to departments, cost centers, and locations.
 - a. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
 - b. Select an account definition in the result list.
 - c. Select the **Assign organizations** task.
 - d. In the **Remove assignments** pane, remove the relevant departments, cost centers, and locations.
 - e. Save the changes.
4. Remove the account definition's assignments to business roles.
 - a. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
 - b. Select an account definition in the result list.
 - c. Select the **Assign business roles** task.
 - d. In the **Remove assignments** pane, remove the business roles.
 - e. Save the changes.
5. If the account definition was requested through the IT Shop, it must be canceled and removed from all IT Shop shelves.

For more detailed information about unsubscribing requests, see the *One Identity Manager Web Designer Web Portal User Guide*.

To remove an account definition from all IT Shop shelves (role-based login)

- a. In the Manager, select the **Entitlements > Account definitions** category.
- b. Select an account definition in the result list.
- c. Select the **Remove from all shelves (IT Shop)** task.
- d. Confirm the security prompt with **Yes**.
- e. Click **OK**.


The account definition is removed from all shelves by the One Identity Manager Service. At the same time, any requests and assignment requests with this account definition are canceled.

To remove an account definition from all IT Shop shelves (non role-based login)

- a. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
- b. Select an account definition in the result list.
- c. Select the **Remove from all shelves (IT Shop)** task.
- d. Confirm the security prompt with **Yes**.
- e. Click **OK**.

The account definition is removed from all shelves by the One Identity Manager Service. At the same time, any requests and assignment requests with this account definition are canceled.

6. Remove the required account definition assignment. As long as the account definition is required for another account definition, it cannot be deleted. Check all the account definitions.
 - a. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
 - b. Select an account definition in the result list.
 - c. Select the **Change main data** task.
 - d. From the **Required account definition** menu, remove the account definition.
 - e. Save the changes.
7. Remove the account definition's assignments to target systems.
 - a. In the Manager, select the Azure Active Directory tenant in the **Azure Active Directory > Tenants** category.
 - b. Select the **Change main data** task.
 - c. On the **General** tab, remove the assigned account definitions.
 - d. Save the changes.
8. Delete the account definition.

- a. In the Manager, select the **Azure Active Directory > Basic configuration data > Account definitions > Account definitions** category.
- b. Select an account definition in the result list.
- c. Click  to delete an account definition.

Target system managers for Exchange Online

A default application role exists for the target system manager in One Identity Manager. Assign the employees who have permission to edit all Exchange Online objects in One Identity Manager to this application role.

Define additional application roles if you want to limit the permissions for target system managers to individual tenants with Exchange Online. The application roles must be added under the default application role.

For detailed information about implementing and editing application roles, see the *One Identity Manager Authorization and Authentication Guide*.

Implementing application roles for target system managers

1. The One Identity Manager administrator allocates employees to be target system administrators.
2. These target system administrators add employees to the default application role for target system managers.

Target system managers with the default application role are authorized to edit all the Exchange Online objects in One Identity Manager.

3. Target system managers can authorize other employees within their area of responsibility as target system managers and if necessary, create additional child application roles and assign these to individual clients.

Table 9: Default application roles for target system managers

User	Tasks
Target system managers	<p>Target system managers must be assigned to the Target systems Exchange Online application role or a child application role.</p> <p>Users with this application role:</p> <ul style="list-style-type: none"> • Assume administrative tasks for the target system. • Create, change, or delete target system objects. • Edit password policies for the target system. • Prepare groups to add to the IT Shop.

User	Tasks
	<ul style="list-style-type: none"> • Can add employees who have another identity than the Primary identity. • Configure synchronization in the Synchronization Editor and define the mapping for comparing target systems and One Identity Manager. • Edit the synchronization's target system types and outstanding objects. • Authorize other employees within their area of responsibility as target system managers and create child application roles if required.

To initially specify employees to be target system administrators

1. Log in to the Manager as a One Identity Manager administrator (**Base role | Administrators** application role)
2. Select the **One Identity Manager Administration > Target systems > Administrators** category.
3. Select the **Assign employees** task.
4. Assign the employee you want and save the changes.

To add the first employees to the default application as target system managers

1. Log in to the Manager as a target system administrator (**Target systems | Administrators** application role).
2. Select the **One Identity Manager Administration > Target systems > Exchange Online** category.
3. Select the **Assign employees** task.
4. Assign the employees you want and save the changes.

To authorize other employees as target system managers when you are a target system manager

1. Log in to the Manager as a target system manager.
2. Select the application role in the **Azure Active Directory > Basic configuration data > Target system managers** category.
3. Select the **Assign employees** task.
4. Assign the employees you want and save the changes.

To specify target system managers for individual clients

1. Log in to the Manager as a target system manager.
2. Select the **Azure Active Directory > Tenants** category.

3. Select the client in the result list.
4. Select the **Change main data** task.
5. On the **General** tab, select the application role in the **Target system manager (Exchange Online)** menu.

- OR -

Next to the **Target system manager (Exchange Online)** menu, click  to create a new application role.

- a. Enter the application role name and assign the **Target systems | Exchange Online** parent application role.
 - b. Click **OK** to add the new application role.
6. Save the changes.
 7. Assign employees to this application role who are permitted to edit the client in One Identity Manager.

Related topics

- [One Identity Manager users for managing Exchange Online](#) on page 11

Job server for Exchange Online-specific process handling

Servers must be informed of your server functionality in order to handle Exchange Online-specific processes in One Identity Manager. For example, the synchronization server.

You have several options for defining a server's functionality:

- In the Designer, create an entry for the Job server in the **Base Data > Installation > Job server** category. For more information about this, see the *One Identity Manager Configuration Guide*.
- In the Manager, select an entry for the Job server in the **Azure Active Directory > Basic configuration data > Server** category and edit the Job server main data.

Use this task if the Job server has already been declared in One Identity Manager and you want to configure special functions for the Job server.

To edit a Job server and its functions

1. In the Manager, select the **Azure Active Directory > Basic configuration data > Server** category.
2. Select the Job server entry in the result list.
3. Select the **Change main data** task.
4. Edit the Job server's main data.

5. Select the **Assign server functions** task and specify server functionality.
6. Save the changes.

Detailed information about this topic

- [General main data for Job servers](#) on page 77
- [Specifying server functions](#) on page 79

General main data for Job servers

NOTE: All editing options are also available in the Designer under **Base Data > Installation > Job server**.

NOTE: More properties may be available depending on which modules are installed.

Table 10: Job server properties

Property	Meaning
Server	Job server name.
Full server name	Full server name in accordance with DNS syntax. Syntax: <Name of servers>.<Fully qualified domain name>
Target system	Computer account target system.
Language	Language of the server.
Server is cluster	Specifies whether the server maps a cluster.
Server belongs to cluster	Cluster to which the server belongs. NOTE: The Server is cluster and Server belongs to cluster properties are mutually exclusive.
IP address (IPv6)	Internet protocol version 6 (IPv6) server address.
IP address (IPv4)	Internet protocol version 4 (IPv4) server address.
Copy process (source server)	Permitted copying methods that can be used when this server is the source of a copy action. At present, only copy methods that support the Robocopy and rsync programs are supported.

Property Meaning

	<p>If no method is given, the One Identity Manager Service determines the operating system of the server during runtime. Replication is then performed with the Robocopy program between servers with a Windows operating system or with the rsync program between servers with a Linux operating system. If the operating systems of the source and destination servers differ, it is important that the right copy method is applied for successful replication. A copy method is chosen that supports both servers.</p>
Coding	Character set coding that is used to write files to the server.
Parent Job server	Name of the parent Job server.
Executing server	<p>Name of the executing server. The name of the server that exists physically and where the processes are handled.</p> <p>This input is evaluated when the One Identity Manager Service is automatically updated. If the server is handling several queues, the process steps are not supplied until all the queues that are being processed on the same server have completed their automatic update.</p>
Queue	Name of the queue to handle the process steps. The process steps are requested by the Job queue using this queue identifier. The queue identifier is entered in the One Identity Manager Service configuration file.
Server operating system	Operating system of the server. This input is required to resolve the path name for replicating software profiles. The values Win32 , Windows , Linux , and Unix are permitted. If no value is specified, Win32 is used.
Service account data	One Identity Manager Service user account information. In order to replicate between non-trusted systems (non-trusted domains, Linux server), the One Identity Manager Service user information has to be declared for the servers in the database. This means that the service account, the service account domain, and the service account password have to be entered for the server.
One Identity Manager Service installed	<p>Specifies whether a One Identity Manager Service is installed on this server. This option is enabled by the QBM_PJobQueueLoad procedure the moment the queue is called for the first time.</p> <p>The option is not automatically removed. If necessary, you can reset this option manually for servers whose queue is no longer enabled.</p>
Stop One Identity Manager Service	<p>Specifies whether the One Identity Manager Service has stopped. If this option is set for the Job server, the One Identity Manager Service does not process any more tasks.</p> <p>You can make the service start and stop with the appropriate administrative permissions in the Job Queue Info program. For more information, see the <i>One Identity Manager Process Monitoring and Troubleshooting Guide</i>.</p>

Property	Meaning
No automatic software update	Specifies whether to exclude the server from automatic software updating. NOTE: Servers must be manually updated if this option is set.
Software update running	Specifies whether a software update is currently running.
Server function	Server functionality in One Identity Manager. One Identity Manager processes are handled with respect to the server function.

Related topics

- [Specifying server functions](#) on page 79

Specifying server functions

NOTE: All editing options are also available in the Designer under **Base Data > Installation > Job server**.

The server function defines the functionality of a server in One Identity Manager. One Identity Manager processes are handled with respect to the server function.

NOTE: More server functions may be available depending on which modules are installed.

Table 11: Permitted server functions

Server function	Remark
Azure Active Directory connector (via Microsoft Graph)	Server on which the Azure Active Directory connector is installed. This server synchronizes the Azure Active Directory target system.
Exchange Online connector (via Windows PowerShell)	This server can connect to the Exchange Online endpoint.
CSV connector	Server on which the CSV connector for synchronization is installed.
Domain controller	The Active Directory domain controller. Servers that are not labeled as domain controllers are considered to be member servers.
Printer server	Server that acts as a print server.
Generic server	Server for generic synchronization with a custom target system.

Server function	Remark
Home server	Server for adding home directories for user accounts.
Update server	<p>This server automatically updates the software on all the other servers. The server requires a direct connection to the database server that One Identity Manager database is installed on. It can run SQL tasks.</p> <p>The server with the One Identity Manager database installed on it is labeled with this functionality during initial installation of the schema.</p>
SQL processing server	<p>It can run SQL tasks. The server requires a direct connection to the database server that One Identity Manager database is installed on.</p> <p>Several SQL processing servers can be set up to spread the load of SQL processes. The system distributes the generated SQL processes throughout all the Job servers with this server function.</p>
CSV script server	This server can process CSV files using the ScriptComponent process component.
Generic database connector	This server can connect to an ADO.Net database.
One Identity Manager database connector	Server on which the One Identity Manager connector is installed. This server synchronizes the One Identity Manager target system.
One Identity Manager Service installed	Server on which a One Identity Manager Service is installed.
Primary domain controller	Primary domain controller.
Profile server	Server for setting up profile directories for user accounts.
SAM synchronization Server	Server for running synchronization with an SMB-based target system.
SMTP host	Server from which One Identity Manager Service sends email notifications. Prerequisite for sending mails using One Identity Manager Service is SMTP host configuration.
Default report server	Server on which reports are generated.
Windows PowerShell connector	The server can run Windows PowerShell version 3.0 or later.

Related topics

- [General main data for Job servers](#) on page 77

Exchange Online organization configuration

The Exchange Online organization configurations of Azure Active Directory tenants are loaded into the One Identity Manager database. It is not possible to customize this information in One Identity Manager due to the complex dependencies and far reaching effects of changes.

Detailed information about this topic

- [Extensions for Azure Active Directory tenants](#) on page 82
- [Exchange Online public folders](#) on page 83
- [Exchange Online policies](#) on page 84

Extensions for Azure Active Directory tenants

For detailed information about Azure Active Directory tenants, see the *One Identity Manager Administration Guide for Connecting to Azure Active Directory*.

The following additional information is mapped to Azure Active Directory tenants for Exchange Online.

- Initial account definition for creating mail contacts (**Mail account definition (initial)**) or mail users (**Mail user definition (initial)**)
This account definition is used if automatic assignment of employees to user accounts is used for this Azure Active Directory tenant and mail contacts or mail users should be created that are already managed (**Linked configured** state). The account definition's default manage level is applied.
- **Target system managers (Exchange Online)**: Application role, in which Exchange Online target system managers are specified for those of the Azure Active Directory tenant. Target system managers must be assigned to the **Target systems**

| **Exchange Online** application role or a child application role.

- Defining categories for the inheritance of entitlements through categories

You can use Office 365 group and mail-enabled distribution group inheritance through categories for Exchange Online.

To edit Azure Active Directory tenant main data

1. In the Manager, select the **Azure Active Directory > Tenants** category.
2. In the result list, select the Azure Active Directory tenant.
3. Select the **Change main data** task.
4. Edit the Azure Active Directory tenant's main data.
5. Save the changes.

Related topics

- [Assigning account definitions to Azure Active Directory tenants](#) on page 71
- [Target system managers for Exchange Online](#) on page 74
- [Exchange Online mail-enabled distribution group inheritance based on categories](#) on page 142
- [Exchange Online Office 365 group inheritance based on categories](#) on page 165

Exchange Online public folders

Public folders are used to allow employees shared access to information. Public folders can be structured hierarchically and are connection with a public folder database.

Exchange Online public folders are loaded into One Identity Manager by synchronization and cannot be edited in One Identity Manager.

To display information about a public folder

1. In the Manager, select the **Azure Active Directory > Tenants > <Azure Active Directory tenant> > Exchange Online administration > Organization configuration > Public folders** category.
2. Select the public folder in the result list.
3. Select one of the following tasks:
 - **Exchange Online public folder overview:** This shows you an overview of the public folder and its dependencies.
 - **Change main data:** This shows the public folder's main data.

Related topics

- [Exchange Online mail-enabled public folders](#) on page 175
- [Synchronizing single objects](#) on page 46

Exchange Online policies

Exchange Online policies are loaded into One Identity Manager by synchronization and cannot be edited in One Identity Manager. You can assign policies to Exchange Online mailboxes.

Sharing administration policies

Sharing policies are implemented to make calendar and contact data available to external users. Assigning a sharing policy to a mailbox regulates how calendar and contact data can be shared with user accounts outside the Exchange Online organization.

Retention policies

Retention policies have been implemented to group settings for retaining folders and email messages and to apply these to mailboxes.

Outlook Web App mailbox policy

Outlook Web App mailbox policies are implemented for managing access to functions in Outlook Web App.

Mobile device mailbox policy

Mailbox policies for mobile email queries contain settings that come into effect when data is accessed with mobile devices through the synchronization protocol Exchange ActiveSync. The settings include, for example, password requirements, specifications for email attachments, device encryption data and access rules for shares.

Role assignment policy

Policies for role assignments have been implemented to provide users with functions and tasks for managing their mailboxes.

To display information about a policy

1. In the Manager, select the **Azure Active Directory > tenants > <Azure Active Directory tenant> > Exchange Online administration > policies > <policy type>**.
2. Select the policy in the result list.
3. Select one of the following tasks:

- **Exchange Online policy overview:** This shows you an overview of the policies and their dependencies.
- **Change main data:** Shows the policy's main data.

Related topics

- [Synchronizing single objects](#) on page 46
- [Policies and features of Exchange Online mailboxes](#) on page 92

Exchange Online mailboxes

Exchange Online mailboxes can send, receive, and save messages. Exchange Online recognizes several mailbox types. The mailbox types listed below are supported in One Identity Manager. Exchange Online mailboxes are loaded into One Identity Manager by synchronization.

Table 12: Supported mailbox types

Mailbox type	Description
User mailbox	<p>User mailboxes are assigned to Azure Active Directory user accounts in an Exchange Online organization.</p> <p>You cannot create user mailboxes in One Identity Manager. User mailboxes are created by assigning the respective subscriptions to Azure Active Directory user accounts. By these means, user mailboxes are created that do not appear in One Identity Manager until after synchronization. The user mailboxes can be subsequently provisioned automatically in Exchange Online.</p>
Equipment mailbox	<p>Equipment mailboxes are resource mailboxes used for planning resources, such as computers or laptops.</p> <p>You can create equipment mailboxes in One Identity Manager. When you create an equipment mailbox, an Azure Active Directory user account is also created and linked to the mailbox.</p>
Room mailbox	<p>Room mailboxes are resource mailboxes used for planning meeting locations.</p> <p>You can room equipment mailboxes in One Identity Manager. When you create a room mailbox, an Azure Active Directory user account is also created and linked to the mailbox.</p>
Shared mailbox	<p>Shared mailboxes are mailboxes that are used by several users.</p> <p>You can create shared mailboxes in One Identity Manager. When you create a shared mailbox, an Azure Active Directory user account is also created and linked to the mailbox.</p>

Mailbox type	Description
Discovery mailbox	In Exchange Online, a discovery mailbox that is used as target mailbox for searches using eDiscovery, is created by default. You cannot edit discovery mailboxes in One Identity Manager.

Detailed information about this topic

- [Creating Exchange Online mailboxes](#) on page 87
- [Editing main data of Exchange Online mailboxes](#) on page 88
- [General main data for Exchange Online mailboxes](#) on page 89
- [Limits and usage of Exchange Online mailboxes](#) on page 91
- [Policies and features of Exchange Online mailboxes](#) on page 92
- [Booking resources for Exchange Online equipment mailboxes and Exchange Online room mailboxes](#) on page 95
- [Adjusting receive restrictions for Exchange Online mailboxes](#) on page 98
- [Customizing send permissions for Exchange Online mailboxes](#) on page 99
- [Specifying moderators for Exchange Online mailboxes](#) on page 100
- [Assigning extended properties to Exchange Online mailbox](#) on page 100
- [Deleting Exchange Online mailboxes](#) on page 101
- [Synchronizing single objects](#) on page 46

Creating Exchange Online mailboxes

Exchange Online mailboxes are loaded into One Identity Manager by synchronization.

You cannot create user mailboxes in One Identity Manager. User mailboxes are created by assigning the respective subscriptions to Azure Active Directory user accounts. By these means, user mailboxes are created that do not appear in One Identity Manager until after synchronization. The user mailboxes can be subsequently provisioned automatically in Exchange Online.

You can create equipment mailboxes, room mailboxes, and shared mailboxes in One Identity Manager. When you create an equipment mailbox, a room mailbox, or a shared mailbox an Azure Active Directory user account is also created and linked to the mailbox.

To create a mailbox

1. In the Manager, select the **Azure Active Directory > Mailboxes** category.
2. Click  in the result list.

3. On the main data form, enter the main data of the mailbox.
4. Save the changes.

Related topics

- [General main data for Exchange Online mailboxes](#) on page 89
- [Limits and usage of Exchange Online mailboxes](#) on page 91
- [Policies and features of Exchange Online mailboxes](#) on page 92
- [Booking resources for Exchange Online equipment mailboxes and Exchange Online room mailboxes](#) on page 95
- [Editing main data of Exchange Online mailboxes](#) on page 88

Editing main data of Exchange Online mailboxes

To edit a mailbox

1. In the Manager, select the **Azure Active Directory > Mailboxes** category.
2. Select the mailbox in the result list and run the **Change main data** task.
3. Edit the mailbox's main data.
4. Save the changes.

Related topics

- [General main data for Exchange Online mailboxes](#) on page 89
- [Limits and usage of Exchange Online mailboxes](#) on page 91
- [Policies and features of Exchange Online mailboxes](#) on page 92
- [Booking resources for Exchange Online equipment mailboxes and Exchange Online room mailboxes](#) on page 95
- [Creating Exchange Online mailboxes](#) on page 87

General main data for Exchange Online mailboxes

Enter the following data on the **General** tab.

Table 13: Mailbox general main data

Property	Description
Employee	Employee using the mailbox.
No link to an employee required	Specifies whether the mailbox is intentionally not assigned an employee. The value is determined from the linked user account.
Not linked to an employee	Indicates why the No link to an employee required option is enabled for this mailbox. The value is determined from the linked user account. Possible values: <ul style="list-style-type: none">• By administrator: The option was set manually by the administrator.• By attestation: The user account was attested.• By exclusion criterion: The user account is not associated with an employee due to an exclusion criterion. For example, the user account is included in the exclude list for automatic employee assignment (configuration parameter PersonExcludeList).
Azure Active Directory tenant	The Azure Active Directory tenant's name.
Azure Active Directory user account	Azure Active Directory user account that uses this mailbox.
Name	Name of the mailbox.
Display name	Name as used in the address book.
Simple display	Simple display name for systems that cannot interpret all the characters of normal display names.
User ID	User ID for the user to log in to the mailbox. Example: <alias>@<domain.com> <user>@yourorganisation.onmicrosoft.com
Alias	Unique email alias for identifying the mailbox.
Proxy	Email addresses for the mailbox. You can also add other mail connectors

Property	Description
addresses	<p>(for example, CCMail, MS) in addition to the standard address type (SMTP, X400).</p> <p>Use the following syntax to set up other proxy addresses:</p> <p>Address type: new email address</p>
Recipient type (detail)	Type of mailbox. Available mailboxes are: User , Room , Equipment , Shared , and Discovery .
Do not display in address list	Specifies whether the mailbox is visible in address books. Set this option if you want to prevent the mailbox from being displayed in address books. This option applies to all address books.
Risk index (calculated)	Maximum risk index value of all assigned groups. The property is only visible if the QER CalculateRiskIndex configuration parameter is set. For detailed information, see the <i>One Identity Manager Risk Assessment Administration Guide</i> .
Category	Categories the mailbox uses to inherit groups. Groups can be selectively inherited by mailboxes. To do this, the groups and mailboxes are divided into categories. Select one or more categories from the menu.
Groups can be inherited	<p>Specifies whether the mailbox can inherit groups through the employee. If the option is set, the mailbox inherits groups through hierarchical roles, in which the employee is a member, or through IT Shop requests.</p> <ul style="list-style-type: none"> • If you add an employee with a mailbox to a department, for example, and you have assigned groups to this department, the mailbox inherits these groups. • If an employee has requested group membership in the IT Shop and the request is granted approval, the employee's mailbox only inherits the group if the option is set.
Send and forward	Specifies whether to send and forward messages. Set this option to send messages to alternative recipients and mailbox owners.
Alternative recipient	<p>Alternative recipient to which messages from this mailbox are forwarded. You can either enter an alternative recipient, a recipient group or a receive folder.</p> <p>To specify an alternative recipient</p> <ol style="list-style-type: none"> 1. Click ➔ next to the field. 2. Select the table under Table which maps the recipient. 3. Select the recipient under Alternative recipient. 4. Click OK.
Sender authentication	Specifies whether authentication data is requested from senders. Set this option to prevent anonymous senders mailing to the mailbox.

Property	Description
required	
Moderation enabled	Specifies whether the mailbox is moderated. Use the Assign moderators task to specify the moderators. Then enable the option.
Sending message	Specifies how senders are notified when they send messages to moderated mailbox. Permitted values are: <ul style="list-style-type: none"> • Do not notify: The sender is not notified. • Only notify senders in your exchange organization: Only internal senders receive a notification. • Notify all senders: Internal and external senders receive notification.
Message read status tracking enabled	Specifies whether this mailbox can show the read status of sent messages.

Related topics

- [Specifying moderators for Exchange Online mailboxes](#) on page 100
- [Assigning Exchange Online mail-enabled distribution groups to Exchange Online recipients](#) on page 129

Limits and usage of Exchange Online mailboxes

The following information is displayed on the **Usage** tab.

Table 14: Limits for a mailbox

Property	Description
Last login	Last time this mailbox was logged in to. This is determined during synchronization and cannot be edited.
Last logout	Last time this mailbox was logged out of. This is determined during synchronization and cannot be edited.
Last logged in user account	Name of the user account that was used for the last login. This data is determined through synchronization and cannot be edited manually.
Storage	Information about the current storage state with respect to the specified

Property	Description
limit status	limits. This data is determined through synchronization and cannot be edited manually.
Number of saved messages	Stored message count This data is determined through synchronization and cannot be edited manually.
Associated items count	Number of associated elements in this mailbox. This is determined during synchronization and cannot be edited.
Used disk space [byte]	Used disk space in bytes. This data is determined through synchronization and cannot be edited manually.
Recoverable items count	Number of items in the Recoverable items folder. This data is determined through synchronization and cannot be edited manually.
Size of recoverable items	Size of messages in the Recoverable items folder. This data is determined through synchronization and cannot be edited manually.
Use default database values	Specifies whether the mailbox database limits are used. This data is determined through synchronization and cannot be edited manually. Option set: Mailbox database limits are in use. Option not set: Mailbox database limits are not in use.
Max. recoverable items	Maximum number of messages allowed in a folder in the Recoverable items folder. This data is determined through synchronization and cannot be edited manually.
Warn at [recoverable items]	Number of items a folder in the Recoverable items folder can contain before a warning is sent to the user. This data is determined through synchronization and cannot be edited manually.
Keep deleted items [days]	Number of days the deleted objects (email message for example) remain on the server before being removed.
Rules quota [KB]	Limit on the number of rules.

Policies and features of Exchange Online mailboxes

Enter the following main data on the **Features** tab.

Table 15: Mailbox features

Property	Description
Sharing policy	Sharing policy which applies for this mailbox.
Role assignment policy	Role assignment policy that applies to this mailbox.
Mobile device mailbox policy	Mobile device mailbox policy that applies to this mailbox.
Outlook Web App mailbox policy	Outlook Web App mailbox policy that applies to this mailbox.
Retention policy	Retention policy applying to this mailbox.
Outlook Web App enabled	Specifies whether the Microsoft Outlook Web App feature is enabled. Office Outlook Web App allows mailbox access over the web browser.
Mobile access	Specifies whether mobile devices can access the mailbox.
Exchange Web Services enabled	Specifies whether the mailbox can be accessed through Exchange Web Services.
IMAP4 enabled	Specifies whether IMAP4 access is enabled.
POP3 enabled	Specifies whether POP3 access is enabled.
MAPI enabled	Specifies whether MAPI access is enabled. MAPI allows mailbox access through a MAPI client, like Outlook.
Calendar repair disabled	Specifies whether it is possible to prevent calendar elements in the mailbox from being repaired by the Calendar Repair Assistant.
Calendar version disabled	Specifies whether it is possible to prevent changes to the calendar being entered in the mailbox.
Archiving enabled	Specifies whether a personal archive is created for this mailbox. Set this option if you want to set up a personal archive for this mailbox.
Archive name	Name of the archive.
Litigation hold	Specifies whether mailbox retention is mandatory.

Property	Description
Put on hold by	The user that enabled litigation hold.
Hold date	Date that litigation hold starts for this mailbox.
Comment for litigation hold	Additional comment with more information to keep the user informed, when the Litigation hold option is set. This data is displayed to the user in Outlook.
Website for litigation hold	Website or document with more information to keep the user informed, when the Litigation hold option is set. This data is displayed to the user in Outlook.
Retention policy hold during this period	Specifies whether retention policy is temporary halted during this period. Set this option if the policy for retention hold needs to be temporarily deferred, for example, during vacation. Specify the time period using the Start date and End date fields.
Start date	Start date on which to hold the retention policy.
End date	Date on which to end the retention policy hold.
Audit logging enabled	Specifies whether mailbox audit logging is enabled for this mailbox.
Log administrator actions	Specifies the mailbox operations that are logged for administrators as part of audit logging. For more information about mailbox audit logging and the mailbox actions that are logged, see the Microsoft documentation.
Log deputy actions	Specifies the mailbox operations that are logged for deputies as part of audit logging. For more information about mailbox audit logging and the mailbox actions that are logged, see the Microsoft documentation.
Log owner actions	Specifies the mailbox operations that are logged for owners as part of audit logging. For more information about mailbox audit logging and the mailbox actions that are logged, see the Microsoft documentation.
Keep audit log entries [days]	Maximum age for audit log entries in a mailbox. Log entries that are older than the limit are deleted.

Related topics

- [Exchange Online policies](#) on page 84

Booking resources for Exchange Online equipment mailboxes and Exchange Online room mailboxes

You can configure booking and planning of resources for equipment and room mailboxes. On the **Booking options** tab, enter the following main data.

Table 16: Main data for booking resources

Property	Description
Resource capacity	Resource capacity, for example, the number of seats in a meeting room.
Enable Calendar Attendant	<p>Specifies whether the Resource Booking Attendant is enabled for device mailboxes and room mailboxes so that booking requests can be processed automatically.</p> <p>Permitted values are:</p> <ul style="list-style-type: none">• Calender Attendant not enabled: The calendar attendant is not activated.• Calender Attendant enabled: The calendar attendant is activated.• Resource booking attendant enabled: The resource booking attendant is automatically enabled for mailboxes of type Room.
Allow reoccurring requests	Specifies whether a series of meetings is allowed.
Request only possible during working hours	Specifies whether the resource can be booked during working hours or outside them, as well.
Reject repeated meeting after max. planning period	Specifies whether booking series can be set up beyond the planning period.
Max. booking window [days]	Maximum planning period for meeting request in days.
Max. duration [min]	Maximum time allowed booking the resource.
Booking permissions for everyone	<p>Specifies whether meeting requests conforming to policy are automatically approved for all users.</p> <p>If this option is not set, use Assign booking permissions to specify individual users who can send requests conforming to policy, which are automatically approved.</p>

Property	Description
Booking permissions for everyone	Specifies whether all users can send booking requests that conform to policy. If this option is not set, use Assign in-policy meeting request permissions to specify individual users who can send requests which are policy non-conform.
Out-of-policy request permissions for everyone	Specifies whether all user can send meeting requests that do not conform to policy. If this option is not set, use Assign out-of-policy meeting request permission to specify individual users who can send requests which are policy non-conform.
Allow conflicts	Specifies whether conflicting meeting requests are allowed.
Max. series conflicts [%]	Threshold in percent for the permitted conflicts of meetings series that overlap with other meetings. If this value is exceeded, the series request is denied.
Max. conflicting instances	Maximum conflicts permitted for meeting series which overlap with other meetings. If the value is exceeded, the series request is denied.
Forward meeting requests	Specifies whether meeting requests are forwarded to the resource mailbox deputy managers. The deputy decides about the meeting request.
Permit meeting requests from external senders	Specifies whether meeting requests from external senders are entered in the calendar.
Add organizer's name to subject	Specifies whether the organizer's name is given in the meeting request's subject field.
Inform organizer about declined meeting request	Specifies whether the organizer is sent information when a meeting request is declined because of conflicts.
Send additional information about rejected request	Specifies whether additional information is sent in response to a meeting request. Enter the additional information in the Additional information input field.
Additional data	Additional information for responding to meeting requests.
Remove attachments from meeting requests	Specifies whether attachments are deleted from meeting requests.
Remove comments from meeting requests	Specifies whether message text is deleted from meeting requests.
Remove subject from	Specifies whether the subject is deleted from meeting requests.

Property	Description
meeting requests	
Only retain calendar meetings	Specifies whether elements that do not belong the calendar are deleted.
Response details enabled	Specifies whether the reasons for accepting or decline a meeting are added to the response email.
New meeting requests are marked with the status "tentative".	Specifies whether meeting requests are automatically entered in the calendar with the Tentative status.
Mark meeting requests as "Tentative"	Specifies whether meeting requests are marked with Tentative status in the calendar. If this option is disabled, meeting requests are marked with the Free status.
Remove "private" flag from accepted meeting	Specifies whether the Private status is deleted from meeting requests.
Delete expired meeting requests	Specifies whether to automatically delete messages to other attendees about forwarded meetings. These messages are moved to the Deleted items folder.
Delete expired meeting requests	Specifies whether to automatically delete old meeting requests from the calendar.

Related topics

- [Booking permissions for Exchange Online equipment mailbox and Exchange Online room mailbox](#) on page 97

Booking permissions for Exchange Online equipment mailbox and Exchange Online room mailbox

You can configure booking permissions of resources for equipment and room mailboxes.

Assuming that booking a resource is not going to result in a planning conflict or the resource's limits being exceeded, like the room capacity or the planned duration, you can allow meeting requests to be automatically approved.

Automatically approve meeting request if the resource is available

- If the **Booking permissions for everyone** option is set, every user can automatically reserve the resource with a meeting request that conform to the

policy.

- Use the **Assign booking permissions** options to specify individual users whose meeting requests are automatically approved.

Allow meeting requests if the resource is available

- If the **Booking permissions for everyone** option is set, all users that adhere to the guidelines, are allowed to send meeting requests.
- Use the **Assign in-policy meeting request permissions** to specify individual users who can send requests which do not conform to the policies.

Automatically approve meeting requests if the resource is available and send meeting requests if the resource is not available.

- If the **Out-of-policy request permissions for everyone** is set, every user can automatically reserve the resource using a meeting request that conforms to the policy. Users can send meeting requests that do not conform to the policies. Meeting requests that do not fulfill the policies can be approved by the mailbox's delegate.
- Use the **Assign out-of-policy meeting request permissions** to specify individual users whose policy conform meeting requests are automatically approved and who can send meeting requests that do not conform to the policies. Meeting requests that do not fulfill the policies can be approved by the mailbox's delegate.

Adjusting receive restrictions for Exchange Online mailboxes

NOTE: The **Assign mail acceptance** and **Assign mail rejection** assignments are mutually exclusive. You can specify whether to accept or deny the recipient's message.


To adjust mail acceptance for mailboxes

1. In the Manager, select the **Azure Active Directory > Mailboxes** category.
2. Select a mailbox in the result list.
3. Select the **Assign mail acceptance** task to specify recipients whose messages are accepted.
- OR -
Select the **Assign mail rejection** task to specify recipients whose messages are rejected.
4. Select the table containing the recipient from the menu at the top of the form. You have the following option:

- Mail-enabled distribution groups
 - Dynamic distribution groups
 - Mailboxes
 - Mail users
 - Mail contacts
 - Office 365 groups
5. In the **Add assignments** pane, assign recipients.

TIP: In the **Remove assignments** pane, you can remove assigned recipients.

To remove an assignment

 - Select the recipient and double-click .
 6. Save the changes.

Customizing send permissions for Exchange Online mailboxes


You use the **Send on behalf of** send permissions to specify which users can send messages on behalf of the mailbox owner.

To customize send permissions for mailboxes

1. In the Manager, select the **Azure Active Directory > Mailboxes** category.
2. Select a mailbox in the result list.
3. Select the **Assign send authorizations** task.
4. Select the table which contains the user from the menu at the top of the form. You have the following options:
 - Mail-enabled distribution groups
 - Mailboxes
 - Mail users
5. In the **Add assignments** pane, assign users.

TIP: In the **Remove assignments** pane, you can remove assigned users.

To remove an assignment

 - Select the user and double-click .
6. Save the changes.

Specifying moderators for Exchange Online mailboxes


Moderated mailboxes are implemented to allow messages sent to a mailbox to be approved or denied by a moderator. The message is not sent on until it has been approved by the moderator.

To specify moderators for a mailbox

1. In the Manager, select the **Azure Active Directory > Mailboxes** category.
2. Select a mailbox in the result list.
3. Select the **Assign moderators** task.
4. Select the table which contains the user from the menu at the top of the form. You have the following options:
 - Mailboxes
 - Mail contacts
 - Mail users
5. In the **Add assignments** pane, add the moderators.

TIP: In the **Remove assignments** pane, you can remove assigned moderators.

To remove an assignment

- Select the moderator and double-click .
6. Save the changes.

Assigning extended properties to Exchange Online mailbox

Extended properties are meta objects, such as operating codes, cost codes, or cost accounting areas that cannot be mapped directly in One Identity Manager.


For more information about using extended properties, see the *One Identity Manager Identity Management Base Module Administration Guide*.

To specify extended properties for a mailbox

1. In the Manager, select the **Azure Active Directory > Mailboxes** category.
2. Select a mailbox in the result list.
3. Select the **Assign extended properties** task.
4. In the **Add assignments** pane, assign extended properties.

TIP: In the **Remove assignments** pane, you can remove assigned extended properties.

To remove an assignment


- Select the extended property and double-click .
5. Save the changes.

Deleting Exchange Online mailboxes

User mailboxes are deleted by removing the subscriptions from their Azure Active Directory user accounts.

You can delete equipment mailboxes, room mailboxes, and shared mailboxes in One Identity Manager. When equipment mailboxes, room mailboxes, or shared mailboxes are deleted, the Azure Active Directory user account linked to the mailbox is deleted at the same time.

To delete a mailbox

1. In the Manager, select the **Azure Active Directory > Mailboxes** category.
2. Select a mailbox in the result list.
3. Click  in the result list.
4. Confirm the security prompt with **Yes**.

Exchange Online mail users

Mail users obtain information about users from outside the Exchange Online organization. Mail users are assigned at least one email address. Notification is automatically forwarded to this email address. As opposed to mail contacts, mail contacts have login credentials and access to resources.

Mail users are loaded into One Identity Manager by synchronization. You can create and edit mail users in One Identity Manager. When you create a mail user, an Azure Active Directory user account is also created and linked to the mail user.

NOTE: It is recommended to use account definitions to set up mail users for company employees.

- In order to create mail users through account definitions, employees must have a central user account and obtain the IT operating data through assignment to a primary department, primary location, or a primary cost center.
- Some of the mail user's main data is mapped from employee main data using templates.

Detailed information about this topic

- [Account definitions for Exchange Online mail users and Exchange Online mail contacts](#) on page 54
- [Creating Exchange Online mail users](#) on page 103
- [Editing main data of Exchange Online mail users](#) on page 103
- [Main data for Exchange Online mail users](#) on page 104
- [Receive restrictions for Exchange Online mail users](#) on page 109
- [Customizing send permissions for Exchange Online mail users](#) on page 109
- [Specifying moderators for Exchange Online mail users](#) on page 110
- [Assigning extended properties to Exchange Online mail users](#) on page 111
- [Deleting Exchange Online mail users](#) on page 111
- [Synchronizing single objects](#) on page 46

Creating Exchange Online mail users


When you create a mail user, an Azure Active Directory user account is also created and linked to the mail user.

Azure Active Directory configuration settings are used for generating random passwords for new mail users, for sending login credentials, and for applying password policies. For more information, see the *One Identity Manager Administration Guide for Connecting to Azure Active Directory*.

NOTE: It is recommended to use account definitions to set up mail users for company employees.

- In order to create mail users through account definitions, employees must have a central user account and obtain the IT operating data through assignment to a primary department, primary location, or a primary cost center.
- Some of the mail user's main data is mapped from employee main data using templates.

To create a mail user

1. In the Manager, select the **Azure Active Directory > Mail users** category.
2. Click  in the result list.
3. On the main data form, enter the main data for the mail user.
4. Save the changes.

Related topics

- [Account definitions for Exchange Online mail users and Exchange Online mail contacts](#) on page 54
- [Editing main data of Exchange Online mail users](#) on page 103
- [Main data for Exchange Online mail users](#) on page 104

Editing main data of Exchange Online mail users

To edit a mail user.

1. In the Manager, select the **Azure Active Directory > Mail users** category.
2. Select the mail user in the result list and run the **Change main data** task.
3. Edit the mail user's main data.
4. Save the changes.

Related topics

- [Creating Exchange Online mail users](#) on page 103
- [Main data for Exchange Online mail users](#) on page 104

Main data for Exchange Online mail users

Table 17: Mail user main data

Property	Description
Employee	Employee to use the mail user. An employee is already entered if the mail user was generated by an account definition. If you create the mail user manually, you can select an employee in the menu.
No link to an employee required	Specifies whether the mail user is intentionally not assigned an employee. The value is determined from the linked user account.
Not linked to an employee	<p>Indicates why the No link to an employee required option is enabled for this mail user. The value is determined from the linked user account. Possible values:</p> <ul style="list-style-type: none">• By administrator: The option was set manually by the administrator.• By attestation: The user account was attested.• By exclusion criterion: The user account is not associated with an employee due to an exclusion criterion. For example, the user account is included in the exclude list for automatic employee assignment (configuration parameter PersonExcludeList).
Account definition	<p>Account definition through which the mail user was created.</p> <p>Use the account definition to automatically populate mail user main data and to specify a manage level for the mail user. One Identity Manager finds the IT operating data of the assigned employee and uses it to populate the corresponding fields in the mail user.</p> <p>NOTE: The account definition cannot be changed once the mail user has been saved.</p>
Manage level	Manage level with which the mail user is created. Select a manage level from the menu. You can only specify the manage level can if you have also entered an account definition. All manage levels of the selected account definition are available in the menu.
Azure Active	The Azure Active Directory tenant's name.

Property	Description
Directory tenant	
Azure Active Directory user account	Azure Active Directory user account that uses this mail user.
First name	The user's first name. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Last name	The user's last name. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Initials	The user's initials. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Name	The mail user's identifier.
Display name	Name as used in the address book.
Alias	Unique alias for further identification of the mail user.
User ID	<p>User ID that user uses to log in.</p> <p>Example:</p> <pre><alias><domain.com> <user>@yourorganisation.onmicrosoft.com</pre>
Password	<p>Login password. The employee's central password can be mapped to the mail user's password. For more information about an employee's central password, see <i>One Identity Manager Identity Management Base Module Administration Guide</i>.</p> <p>NOTE: One Identity Manager password policies are taken into account when a user password is being verified. Ensure that the password policy does not violate the target system's requirements.</p> <p>Azure Active Directory configuration settings are used for generating random passwords for new mail users, for sending login credentials, and for applying password policies. For more information, see the <i>One Identity Manager Administration Guide for Connecting to Azure Active Directory</i>.</p>
Confirmation	Reconfirm password.
Proxy addresses	<p>Other email addresses for the mail user. Use the following syntax to set up other proxy addresses:</p> <p>Address type: new email address</p>
Recipient type (detail)	Type of mail user. You can select either Mail users or Guest mail users .

Property	Description
External email address	Email address for forwarding messages.
Destination address type	Address type of the email address. Permitted value is SMTP .
Do not display in address list	Specifies whether the mail user is visible in address books. Set this option if you want to prevent the mail user from being displayed in address books. This option applies to all address books.
Risk index (calculated)	Maximum risk index value of all assigned groups. The property is only visible if the QER CalculateRiskIndex configuration parameter is set. For detailed information, see the <i>One Identity Manager Risk Assessment Administration Guide</i> .
Category	Categories the mail user uses to inherit groups. Groups can be selectively inherited by mail users. To do this, the groups and mail users are divided into categories. Select one or more categories from the menu.
Groups can be inherited	<p>Specifies whether the mail user can inherit groups through the employee. If the option is set, the mail user inherits groups through hierarchical roles, in which the employee is a member, or through IT Shop requests.</p> <ul style="list-style-type: none"> • If you add an employee with a user accounts to, for example, a department and you have assigned groups to this department, the mail user inherits these groups. • If an employee has requested group membership in the IT Shop and the request is granted approval, the employee's mail user only inherits the group if the option is set.
Simple display	Simple display name for systems that cannot interpret all the characters of normal display names.
Phonetic display name	Specifies an alternative way of writing the name that is used in text-to-speech in Unified Messaging (UM). For example, it is used if the pronunciation and spelling of the name do not match.
Sort order	Order of displaying in a hierarchical address book.
Message format	Format for messages that are sent to mail u. Permitted values are MIME (default) and Text .
Message body format	<p>Format for body text of messages that are sent to mail users. Options are Text, HTML and TextAndHtml. The permitted values depend on the selected message format.</p> <ul style="list-style-type: none"> • If the MIME message formation is fixed, the format of the body text can be Text, HTML and TextAndHtml (default). • If the message format is Text, the format of the body text can be Text.

Property	Description
Attachment format	The Apple Macintosh operating system's attachment format for messages that are sent to mail users. Options are BinHex (default), UuEncode , AppleSingle , and AppleDouble .
Use preferred message format	Specifies whether message format settings configured for the recipient are overwritten by the global settings.
Use MAPI-RTF	Specifies whether the mail user can receive messages in MAPI format. Available options are Never , Always , and Use default settings .
Sender authentication required	Specifies whether authentication data is requested from senders. Set this option to prevent anonymous senders mailing the mail user.
Moderation enabled	Specifies whether the mail user is moderated. Use the Assign moderators task to specify the moderators. Then enable the option.
Sending message	Specifies how senders are notified when they send messages to moderated mail users. Permitted values are: <ul style="list-style-type: none"> • Do not notify: The sender is not notified. • Only notify senders in your exchange organization: Only internal senders receive a notification. • Notify all senders: Internal and external senders receive notification.
Street	Street or road. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
City	City. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level. Locations can be automatically generated and employees assigned based on the city.
Mailbox	Mailbox. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
State	State. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Zip code	Zip code. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Country or region	The country ID.
Office	Office address.
Business phone	Business telephone numbers. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.

Property	Description
Additional phone numbers	Other business telephone numbers.
Fax	Fax number. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Additional fax numbers	Additional fax numbers.
Home phone	Private telephone number.
Additional private numbers	Additional telephone numbers.
Mobile phone	Mobile number. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Mobile phone	Mobil phone number.
Website.	The user's website.
Notes	More information about the user.
Item	The user's job title.
Department	Department. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Company	Company. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Manager	<p>Manager responsible for the mail user.</p> <p>To specify a manager</p> <ol style="list-style-type: none"> 1. Click ➔ next to the field. 2. In the Table menu, select the table that maps the account manager. 3. In the Account manager menu, select the manager. 4. Click OK.
Assistant	Name of the mail contact's assistant.

Related topics

- [Account definitions for Exchange Online mail users and Exchange Online mail contacts](#) on page 54
- [Specifying moderators for Exchange Online mailboxes](#) on page 100
- [Assigning Exchange Online mail-enabled distribution groups to Exchange Online recipients](#) on page 129

Receive restrictions for Exchange Online mail users

NOTE: The **Assign mail acceptance** and **Assign mail rejection** assignments are mutually exclusive. You can specify whether to accept or deny the recipient's message.

To customize mail acceptance for a mail user

1. In the Manager, select the **Azure Active Directory > Mail user** category.
2. Select the mail user in the result list.
3. Select the **Assign mail acceptance** task to specify recipients whose messages are accepted.


- OR -

Select the **Assign mail rejection** task to specify recipients whose messages are rejected.

4. Select the table containing the recipient from the menu at the top of the form. You have the following options:
 - Mail-enabled distribution groups
 - Dynamic distribution groups
 - Mailboxes
 - Mail users
 - Mail contacts
 - Office 365 groups
5. In the **Add assignments** pane, assign recipients.

TIP: In the **Remove assignments** pane, you can remove assigned recipients.

To remove an assignment

- Select the recipient and double-click .
6. Save the changes.

Customizing send permissions for Exchange Online mail users


You use the **Send on behalf of** send permissions to specify which users can send messages on behalf of the mail users.

To customize send permissions for a mail user

1. In the Manager, select the **Azure Active Directory > Mail users** category.
2. Select the mail user in the result list.
3. Select the **Assign send authorizations** task.
4. Select the table which contains the user from the menu at the top of the form. You have the following options:
 - Mail-enabled distribution groups
 - Mailboxes
 - Mail users
5. In the **Add assignments** pane, assign users.

TIP: In the **Remove assignments** pane, you can remove assigned users.

To remove an assignment

- Select the user and double-click .
6. Save the changes.

Specifying moderators for Exchange Online mail users


Moderated mail users are implemented to accept or reject messages sent to a mail user by a moderator. The message is not sent on until it has been approved by the moderator.

To specify moderators for a mail user

1. In the Manager, select the **Azure Active Directory > Mail users** category.
2. Select the mail user in the result list.
3. Select the **Assign moderators** task.
4. Select the table which contains the user from the menu at the top of the form. You have the following options:
 - Mailboxes
 - Mail contacts
 - Mail users
5. In the **Add assignments** pane, add the moderators.

TIP: In the **Remove assignments** pane, you can remove assigned moderators.

To remove an assignment

- Select the moderator and double-click .
6. Save the changes.

Assigning extended properties to Exchange Online mail users

Extended properties are meta objects, such as operating codes, cost codes, or cost accounting areas that cannot be mapped directly in One Identity Manager.


For more information about using extended properties, see the *One Identity Manager Identity Management Base Module Administration Guide*.

To specify extended properties for a mail user

1. In the Manager, select the **Azure Active Directory > Mail users** category.
2. Select the mail user in the result list.
3. Select **Assign extended properties**.
4. In the **Add assignments** pane, assign extended properties.

TIP: In the **Remove assignments** pane, you can remove assigned extended properties.

To remove an assignment


- Select the extended property and double-click .
5. Save the changes.

Deleting Exchange Online mail users

When you delete a mail user, the **Do not display in address lists** option is enabled and the mail user is no longer shown in address books. In addition, the Azure Active Directory user account that is linked to the mail user is deleted.

NOTE: As long as an account definition for an employee is valid, the employee retains the mail user that was created by it. If the account definition assignment is removed, the mail user created through this account definition, is deleted.

To delete a mail user

1. In the Manager, select the **Azure Active Directory > Mail users** category.
2. Select the mail user in the result list.
3. Click  in the result list.
4. Confirm the security prompt with **Yes**.

Exchange Online mail contacts

Mail contacts obtain information about users from outside the Exchange Online organization. Mail contacts are assigned at least one email address. Notification is automatically forwarded to this email address. As opposed to mail users, mail contacts do not have login credentials or access to resources.

Mail contacts are loaded into One Identity Manager by synchronization. You can create and edit mail contacts in One Identity Manager.

NOTE: It is recommended to use account definitions to set up mail contacts for company employees.

- In order to create mail contacts through account definitions, employees must have a central user account and a default email address and obtain their IT operating data through assignment to a primary department, primary location, or a primary cost center.
- Some of the mail contact's main data is mapped from employee main data using templates.

Detailed information about this topic


- [Account definitions for Exchange Online mail users and Exchange Online mail contacts](#) on page 54
- [Creating Exchange Online mail contacts](#) on page 113
- [Editing main data of Exchange Online mail contacts](#) on page 113
- [Main data for Exchange Online mail contacts](#) on page 114
- [Receive restrictions for Exchange Online mail contacts](#) on page 118
- [Customizing send permissions for Exchange Online mail contacts](#) on page 119
- [Specifying moderators for Exchange Online mail contacts](#) on page 120
- [Assigning extended properties to Exchange Online mail contacts](#) on page 120
- [Deleting Exchange Online mail contacts](#) on page 121
- [Synchronizing single objects](#) on page 46

Creating Exchange Online mail contacts

NOTE: It is recommended to use account definitions to set up mail contacts for company employees.

- In order to create mail contacts through account definitions, employees must have a central user account and a default email address and obtain their IT operating data through assignment to a primary department, primary location, or a primary cost center.
- Some of the mail contact's main data is mapped from employee main data using templates.

To create a mail contact

1. In the Manager, select the **Azure Active Directory > Mail contacts** category.
2. Click  in the result list.
3. On the main data form, enter the main data for the mail contact.
4. Save the changes.

Related topics

- [Account definitions for Exchange Online mail users and Exchange Online mail contacts](#) on page 54
- [Editing main data of Exchange Online mail contacts](#) on page 113
- [Main data for Exchange Online mail contacts](#) on page 114

Editing main data of Exchange Online mail contacts

To edit a mail contact

1. In the Manager, select the **Azure Active Directory > Mail contacts** category.
2. Select the mail contact in the result list and run the **Change main data** task.
3. Edit the mail contact's main data.
4. Save the changes.

Related topics

- [Creating Exchange Online mail contacts](#) on page 113
- [Main data for Exchange Online mail contacts](#) on page 114

Main data for Exchange Online mail contacts

Table 18: Mail contacts main data

Property	Description
Employee	Employee to use the mail contact. An employee is already entered if the mail contact was generated by an account definition. If you create the mail contact manually, you can select an employee in the menu.
No link to an employee required	<p>Specifies whether the contact is intentionally not assigned an employee. The option is automatically set if a contact is included in the exclusion list for automatic employee assignment or a corresponding attestation is carried out. You can set the option manually. Enable the option if the contact does not need to be linked with an employee (for example, if several employees use the contact).</p> <p>If attestation approves these contacts, these contacts will not be submitted for attestation in the future. In the Web Portal, contact that are not linked to an employee can be filtered according to various criteria.</p>
Not linked to an employee	<p>Indicates why the No link to an employee required option is enabled for this contact. Possible values:</p> <ul style="list-style-type: none">• By administrator: The option was set manually by the administrator.• By attestation: The contact was attested.• By exclusion criterion: The contact is not associated with an employee due to an exclusion criterion. For example, the contact is included in the exclude list for automatic employee assignment (configuration parameter PersonExcludeList).
Account definition	<p>Account definition through which the mail contact was created.</p> <p>Use the account definition to automatically populate mail contact main data and to specify a manage level for the mail contact. One Identity Manager finds the IT operating data of the assigned employee and uses it to populate the corresponding fields in the mail contact.</p> <p>NOTE: The account definition cannot be changed once the mail contact has been saved.</p>
Manage level	Manage level with which the mail contact is created. Select a manage level from the menu. You can only specify the manage level can if you have also entered an account definition. All manage levels of the selected account definition are available in the menu.
Azure Active Directory	The Azure Active Directory tenant's name.

Property	Description
tenant	
First name	The contact's first name. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Last name	The contact's last name. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Initials	The contact's initials. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Name	The mail contact's identifier.
Display name	Name as used in the address book.
Alias	Unique alias for further identification of the mail contact.
Proxy addresses	Other email addresses for the mail contact. Use the following syntax to set up other proxy addresses: Address type: new email address
External email address	Email address for forwarding messages.
Destination address type	Address type of the email address. Permitted value is SMTP .
Do not display in address list	Specifies whether the mail contact is visible in address books. Set this option if you want to prevent the mail contact from being displayed in address books. This option applies to all address books.
Risk index (calculated)	Maximum risk index value of all assigned groups. The property is only visible if the QER CalculateRiskIndex configuration parameter is set. For detailed information, see the <i>One Identity Manager Risk Assessment Administration Guide</i> .
Category	Categories the mail contact uses to inherit groups. Groups can be selectively inherited by mail contacts. To do this, the groups and mail contacts are divided into categories. Select one or more categories from the menu.
Groups can be inherited	Specifies whether the mail contact can inherit groups through the employee. If the option is set, the mail contact inherits groups through hierarchical roles, in which the employee is a member, or through IT Shop requests. <ul style="list-style-type: none"> • If you add an employee with a user accounts to, for example, a department and you have assigned groups to this department, the mail contact inherits these groups. • If an employee has requested group membership in the IT Shop and the request is granted approval, the employee's mail contact

Property	Description
	only inherits the group if the option is set.
Simple display	Simple display name for systems that cannot interpret all the characters of normal display names.
Phonetic display name	Specifies an alternative way of writing the name that is used in text-to-speech in Unified Messaging (UM). For example, it is used if the pronunciation and spelling of the name do not match.
Sort order	Order of displaying in a hierarchical address book.
Message format	Format for messages that are sent to mail contacts. Permitted values are MIME (default) and Text .
Message body format	<p>Format for body text of messages that are sent to mail contacts. Options are Text, HTML and TextAndHtml. The permitted values depend on the selected message format.</p> <ul style="list-style-type: none"> • If the MIME message formation is fixed, the format of the body text can be Text, HTML and TextAndHtml (default). • If the message format is Text, the format of the body text can be Text.
Attachment format	The Apple Macintosh operating system's attachment format for messages that are sent to mail contacts. Options are BinHex (default), UuEncode , AppleSingle , and AppleDouble .
Use preferred message format	Specifies whether message format settings configured for the recipient are overwritten by the global settings.
Use MAPI-RTF	Specifies whether the mail contact can receive messages in MAPI format. Available options are Never , Always , and Use default settings .
Sender authentication required	Specifies whether authentication data is requested from senders. Set this option to prevent anonymous senders mailing the mail contact.
Moderation enabled	Specifies whether the mail contact is moderated. Use the Assign moderators task to specify the moderators. Then enable the option.
Sending message	<p>Specifies how senders are notified when they send messages to moderated mail contacts. Permitted values are:</p> <ul style="list-style-type: none"> • Do not notify: The sender is not notified. • Only notify senders in your exchange organization: Only internal senders receive a notification. • Notify all senders: Internal and external senders receive notification.

Property	Description
Street	Street or road. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
City	City. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level. Locations can be automatically generated and employees assigned based on the city.
Mailbox	Mailbox. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
State	State. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Zip code	Zip code. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Country or region	The country ID.
Office	Office address.
Business phone	Business telephone numbers. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Additional phone numbers	Other business telephone numbers.
Fax	Fax number. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Additional fax numbers	Additional fax numbers.
Home phone	Private telephone number.
Additional private numbers	Additional telephone numbers.
Mobile phone	Mobile number. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Mobile phone	Mobil phone number.
Web page	Contact's web page.
Notes	More information about the contact.
Title	The contact's job title.
Department	Department. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.

Property	Description
Company	Company. If you have assigned an account definition, the input field is automatically filled out with respect to the manage level.
Manager	<p>Manager responsible for the mail contact.</p> <p>To specify a manager</p> <ol style="list-style-type: none"> 1. Click ➔ next to the field. 2. In the Table menu, select the table that maps the account manager. 3. In the Manager menu, select the manager. 4. Click OK.
Assistant	Name of the mail contact's assistant.
Assistant phone	Telephone number of the assistant.

Related topics

- [Account definitions for Exchange Online mail users and Exchange Online mail contacts](#) on page 54
- [Specifying moderators for Exchange Online mail contacts](#) on page 120
- [Assigning Exchange Online mail-enabled distribution groups to Exchange Online recipients](#) on page 129

Receive restrictions for Exchange Online mail contacts

NOTE: The **Assign mail acceptance** and **Assign mail rejection** assignments are mutually exclusive. You can specify whether to accept or deny the recipient's message.


To customize mail acceptance for a mail contact

1. In the Manager, select the **Azure Active Directory > Mail contacts** category.
 2. Select the mail contact in the result list.
 3. Select the **Assign mail acceptance** task to specify recipients whose messages are accepted.
- OR -
- Select the **Assign mail rejection** task to specify recipients whose messages are rejected.

4. Select the table containing the recipient from the menu at the top of the form. You have the following option:
 - Mail-enabled distribution groups
 - Dynamic distribution groups
 - Mailboxes
 - Mail users
 - Mail contacts
 - Office 365 groups
5. In the **Add assignments** pane, assign recipients.

TIP: In the **Remove assignments** pane, you can remove assigned recipients.

To remove an assignment

 - Select the recipient and double-click .
6. Save the changes.

Customizing send permissions for Exchange Online mail contacts


You use the **Send on behalf of** send permissions to specify which users can send messages on behalf of the mail contacts.

To customize send permissions for a mail contact

1. In the Manager, select the **Azure Active Directory > Mail contacts** category.
2. Select the mail contact in the result list.
3. Select the **Assign send authorizations** task.
4. Select the table which contains the user from the menu at the top of the form. You have the following option:
 - Mail-enabled distribution groups
 - Mailboxes
 - Mail users
5. In the **Add assignments** pane, assign users.

TIP: In the **Remove assignments** pane, you can remove assigned users.

To remove an assignment

 - Select the user and double-click .
6. Save the changes.

Specifying moderators for Exchange Online mail contacts


Moderated mail contacts are implemented to accept or reject messages sent to a mail contacts by a moderator. The message is not sent on until it has been approved by the moderator.

To specify moderators for a mail contact

1. In the Manager, select the **Azure Active Directory > Mail contacts** category.
2. Select the mail contact in the result list.
3. Select the **Assign moderators** task.
4. Select the table which contains the user from the menu at the top of the form. You have the following options:
 - Mailboxes
 - Mail contacts
 - Mail users
5. In the **Add assignments** pane, add the moderators.

TIP: In the **Remove assignments** pane, you can remove assigned moderators.

To remove an assignment

- Select the moderator and double-click .
6. Save the changes.

Assigning extended properties to Exchange Online mail contacts

Extended properties are meta objects, such as operating codes, cost codes, or cost accounting areas that cannot be mapped directly in One Identity Manager.


For more information about using extended properties, see the *One Identity Manager Identity Management Base Module Administration Guide*.

To specify extended properties for a mail contact

1. In the Manager, select the **Azure Active Directory > Mail contacts** category.
2. Select the mail contact in the result list.
3. Select the **Assign extended properties** task.
4. In the **Add assignments** pane, assign extended properties.

TIP: In the **Remove assignments** pane, you can remove assigned extended properties.

To remove an assignment


- Select the extended property and double-click .
5. Save the changes.

Deleting Exchange Online mail contacts

NOTE: As long as an account definition for an employee is valid, the employee retains the mail contact that was created by it. If the account definition assignment is removed, the mail contact created through this account definition, is deleted.

When you delete a mail contact, the **Do not display in address lists** option is enabled and the mail contact is no longer shown in address books.

To delete a mail contact

1. In the Manager, select the **Azure Active Directory > Mail contacts** category.
2. Select the mail contact in the result list.
3. Click  in the result list.
4. Confirm the security prompt with **Yes**.

Exchange Online mail-enabled distribution groups

You can use mail-enabled universal security groups and mail-enabled universal distribution groups to distribute messages to a group of recipients.

Mail-enabled distribution groups are loaded into One Identity Manager by synchronization. You can create and edit mail-enabled distribution groups in One Identity Manager. When you create a mail-enabled distribution group, an Azure Active Directory group is also created and linked to the mail-enabled distribution group.

In One Identity Manager, you can assign mail-enabled distribution groups directly to mailboxes, mail users, and mail contacts or they can be inherited through departments, cost centers, locations, or business roles. Users can also request mail-enabled distribution groups through the Web Portal. To do this, the mail-enabled distribution groups are supplied by the IT Shop.

Detailed information about this topic


- [Creating Exchange Online mail-enabled distribution groups](#) on page 123
- [Editing main data for Exchange Online mail-enabled distribution groups](#) on page 123
- [Main data for Exchange Online mail-enabled distribution groups](#) on page 124
- [Receive restrictions for Exchange Online mail-enabled distribution groups](#) on page 127
- [Customizing send permissions for Exchange Online mail-enabled distribution groups](#) on page 127
- [Specifying moderators for Exchange Online mail-enabled distribution groups](#) on page 128
- [Specifying Exchange Online mail-enabled distribution groups](#) on page 129
- [Assigning Exchange Online mail-enabled distribution groups to Exchange Online recipients](#) on page 129
- [Exchange Online mail-enabled distribution group inheritance based on categories](#) on page 142

- [Adding Exchange Online dynamic distribution groups to Exchange Online mail-enabled distribution groups](#) on page 143
- [Adding an Exchange Online dynamic distribution group to Exchange Online mail-enabled distribution groups](#) on page 144
- [Adding Exchange Online mail-enabled public folder to Exchange Online mail-enabled distribution groups](#) on page 144
- [Assigning extended properties to Exchange Online mail-enabled distribution groups](#) on page 145
- [Deleting Exchange Online mail-enabled distribution groups](#) on page 145
- [Synchronizing single objects](#) on page 46

Creating Exchange Online mail-enabled distribution groups

When you create a mail-enabled distribution group, an Azure Active Directory group is also created and linked to the mail-enabled distribution group.

To create a mail-enabled distribution group

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Click  in the result list.
3. On the main data form, enter the main data for the mail-enabled distribution group.
4. Save the changes.

Related topics

- [Editing main data for Exchange Online mail-enabled distribution groups](#) on page 123
- [Main data for Exchange Online mail-enabled distribution groups](#) on page 124

Editing main data for Exchange Online mail-enabled distribution groups

To edit a mail-enabled distribution group

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.

2. Select the mail-enabled distribution group in the result list and run the **Change main data** task.
3. Edit the mail-enabled distribution group's main data.
4. Save the changes.

Related topics

- [Creating Exchange Online mail-enabled distribution groups](#) on page 123
- [Main data for Exchange Online mail-enabled distribution groups](#) on page 124

Main data for Exchange Online mail-enabled distribution groups

Table 19: Mail-enabled distribution group main data

Property	Description
Azure Active Directory group	Azure Active Directory group for which the mail-enabled distribution group is created.
Azure Active Directory tenant	The Azure Active Directory tenant's name.
Name	Name of the mail-enabled distribution group.
Display name	Name as used in the address book.
Simple display	Simple display name for systems that cannot interpret all the characters of normal display names.
Alias	Unique alias for further identification of the mail-enabled distribution group.
Group type	The type of group. Permitted values are Universal (default) and Universal, security-enabled .
Proxy addresses	Email addresses for the mail-enabled distribution group. You can also add other mail connectors (for example, CCMail, MS) in addition to the standard address type (SMTP, X400). Use the following syntax to set up other proxy addresses: Address type: new email address
Do not display in address list	Specifies whether the mail-enabled distribution group is visible in address books. Set this option if you want to prevent the mail-enabled distribution group from being displayed in address books. This option applies to all

Property	Description
	address books.
Email address	Email addresses for the mail-enabled distribution group.
Report to sender	Specifies whether the delivery reports are sent to the message sender.
Report to owner	Specifies whether the delivery reports are sent to the message owner.
Only limit messages from authenticated users	Specifies whether authentication data is requested from senders. Set this option if only messages from authenticated users are permitted.
Out-of-office message to sender	Set this option if the message sender should receive out-of-office messages.
Add to group	<p>Specifies how members can join the mail-enabled distribution group. Permitted values are:</p> <ul style="list-style-type: none"> • Open: Members can be added to the group without approval. • Closed: Only mail-enabled distribution group administrators can add members to the group. Requests to be added to the group are automatically denied. • Owner approval: Requests to be added to the group can be made and are approved by the mail-enabled distribution group administrators. <p>Use the Assign administrators task to specify administrators.</p>
Leave group	<p>Use this option to specify how members can leave the distribution group. Permitted values are:</p> <ul style="list-style-type: none"> • Open: Members can leave the group without approval. • Closed: Members can only leave the group with administrator approval. Requests to leave the group are automatically denied. <p>Use the Assign administrators task to specify administrators.</p>
Moderation enabled	Specifies whether the mail-enabled distribution group is moderated. Set this option if the distribution group should be moderated. Use the task Assign moderators to specify moderators.
Allow moderation of child groups	Specifies how to approve messages if a moderate group appears in other moderated groups as a member.

Property	Description
Sending message	<p>Specifies how senders are notified when they send messages to moderated distribution groups. Permitted values are:</p> <ul style="list-style-type: none"> • Do not notify: The sender is not notified. • Only notify senders in your exchange organization: Only internal senders receive a notification. • Notify all senders: Internal and external senders receive notification.
IT Shop	Specifies whether the group can be requested through the IT Shop. If this option is set, the group can be requested by the employees through the Web Portal and distributed with a defined approval process. The group can still be assigned directly to mailboxes, mail users and mail contacts, and to hierarchical roles.
Only for use in IT Shop	Specifies whether the group can only be requested through the IT Shop. If this option is set, the group can be requested by the employees through the Web Portal and distributed with a defined approval process. Direct assignment of the group to hierarchical roles or mailboxes, mail users and mail contacts is not permitted.
Service item	Service item data for requesting the group through the IT Shop.
Risk index	<p>Value for assessing the risk of assigning the group to mailboxes, mail users, and mail contacts. Set a value in the range 0 to 1. This field is only visible if the QER CalculateRiskIndex configuration parameter is set.</p> <p>For more information about risk assessment, see the <i>One Identity Manager Risk Assessment Administration Guide</i>.</p>
Category	Categories used by mailboxes, mail users, and mail contacts to inherit groups. Groups can be selectively inherited by mailboxes, mail users, and mail contacts. To do this, the group and mailboxes, mail users, and mail contacts are divided into categories. Select one or more categories from the menu.

Related topics

- [Specifying moderators for Exchange Online mail-enabled distribution groups](#) on page 128
- [Specifying Exchange Online mail-enabled distribution groups](#) on page 129

Receive restrictions for Exchange Online mail-enabled distribution groups

NOTE: The **Assign mail acceptance** and **Assign mail rejection** assignments are mutually exclusive. You can specify whether to accept or deny the recipient's message.

To modify mail acceptance for mail-enabled distribution groups

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign mail acceptance** task to specify recipients whose messages are accepted.

- OR -


Select the **Assign mail rejection** task to specify recipients whose messages are rejected.

4. Select the table containing the recipient from the menu at the top of the form. You have the following option:
 - Mail-enabled distribution groups
 - Dynamic distribution groups
 - Mailboxes
 - Mail users
 - Mail contacts
 - Office 365 groups

5. In the **Add assignments** pane, assign recipients.

TIP: In the **Remove assignments** pane, you can remove assigned recipients.

To remove an assignment

- Select the recipient and double-click .
6. Save the changes.

Customizing send permissions for Exchange Online mail-enabled distribution groups

Use the **Send on behalf of** send permission to specify which users can send messages on behalf of the distribution group.

To customize send permissions for mail-enabled distribution groups

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign send authorizations** task.
4. Select the table which contains the user from the menu at the top of the form. You have the following option:
 - Mail-enabled distribution groups
 - Mailboxes
 - Mail users
5. In the **Add assignments** pane, assign users.

TIP: In the **Remove assignments** pane, you can remove assigned users.

To remove an assignment

- Select the user and double-click ✓.
6. Save the changes.

Specifying moderators for Exchange Online mail-enabled distribution groups

Moderated distribution groups let a moderator approve or deny messages sent to a mail-enabled distribution group. Only after a message has been approved by a moderator can it be forwarded to members of the mail-enabled distribution group.

To specify moderators for a mail-enabled distribution group

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign moderators** task.
4. Select the table which contains the user from the menu at the top of the form. You have the following options:
 - Mailboxes
 - Mail contacts
 - Mail users
5. In the **Add assignments** pane, add the moderators.

TIP: In the **Remove assignments** pane, you can remove assigned moderators.

To remove an assignment

- Select the moderator and double-click ✓.
6. Save the changes.

Specifying Exchange Online mail-enabled distribution groups

Membership in mail-enabled distribution groups can be applied for and approved. Specify which users manage the mail-enabled distribution group and therefore can grant approval for membership in the group.

To specify a mail-enabled distribution group

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign administrators** task.
4. Select the table which contains the administrators from the menu at the top of the form. You have the following options:
 - Azure Active Directory user accounts
 - Mail-enabled distribution groups
5. In the **Add assignments** pane, assign the administrators.

TIP: In the **Remove assignments** pane, you can remove assigned administrators.

To remove an assignment

- Select the administrator and double-click ✓.
6. Save the changes.

Delete this text and replace it with your own.

Assigning Exchange Online mail-enabled distribution groups to Exchange Online recipients

Exchange Online mail-enabled distribution groups can be assigned directly or indirectly to mailboxes, mail users, and mail contacts.

In the case of indirect assignment, employees and mail-enabled distribution groups are assigned to hierarchical roles, such as departments, cost centers, locations, or business roles. The mail-enabled distribution groups assigned to an employee are calculated from the position in the hierarchy and the direction of inheritance.

- If you add an employee in roles and the employee has a mailbox, the mailbox is added to the mail-enabled distribution groups.
- If you add an employee to roles and that employee has a mail user, the mail user is added to the mail-enabled distribution groups.
- If you add an employee to roles and that employee has a mail contact, the mail contact is added to the mail-enabled distribution groups.

Furthermore, Exchange Online mail-enabled distribution groups can be requested in the Web Portal. To do this, add employees to a shop as customers. All Exchange Online mail-enabled distribution groups that are assigned to this shop as products can be requested by the customers. Requested Exchange Online mail-enabled distribution groups are assigned to the employees after approval is granted.

Through system roles, Exchange Online mail-enabled distribution groups can be grouped together and assigned to employees and workdesks as a package. You can create system roles that contain only Exchange Online mail-enabled distribution groups. You can also group any number of company resources into a system role.

To react quickly to special requests, you can assign Exchange Online mail-enabled distribution groups directly to mailboxes, mail users, and mail contacts.

For detailed information see the following guides:

Topic	Guide
Basic principles for assigning and inheriting company resources	<i>One Identity Manager Identity Management Base Module Administration Guide</i> <i>One Identity Manager Business Roles Administration Guide</i>
Assigning company resources through IT Shop requests	<i>One Identity Manager IT Shop Administration Guide</i>
System roles	<i>One Identity Manager System Roles Administration Guide</i>

Detailed information about this topic

- [Prerequisites for indirect assignment of Exchange Online mail-enabled distribution groups](#) on page 131
- [Assigning Exchange Online mail-enabled distribution groups to departments, cost centers, and locations](#) on page 132
- [Assigning Exchange Online mail-enabled distribution groups to business roles](#) on page 134

- [Adding Exchange Online mail-enabled distribution groups to system roles](#) on page 135
- [Assigning Exchange Online mail-enabled distribution groups to the IT Shop](#) on page 136
- [Assigning Exchange Online recipients to Exchange Online mail-enabled distribution groups](#) on page 139
- [Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mailboxes](#) on page 140
- [Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mail users](#) on page 141
- [Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mail contacts](#) on page 142

Prerequisites for indirect assignment of Exchange Online mail-enabled distribution groups

In the case of indirect assignment, employees and Exchange Online mail-enabled distribution groups are assigned to hierarchical roles, such as departments, cost centers, locations, or business roles. When assigning Exchange Online mail-enabled distribution groups indirectly, check the following settings and modify them if necessary.

1. Assignment of employees and Exchange Online mail-enabled distribution groups is permitted for role classes (departments, cost centers, locations, or business roles).

For more information, see the *One Identity Manager Identity Management Base Module Administration Guide*.

To configure assignments to roles of a role class

- a. In the Manager, select role classes in the **Organizations > Basic configuration data > Role classes** category.
- OR -
In the Manager, select role classes in the **Business roles > Basic configuration data > Role classes** category.
- b. Select the **Configure role assignments** task and configure the permitted assignments.
 - To generally allow an assignment, enable the **Assignments allowed** column.
 - To allow direct assignment, enable the **Direct assignments**

permitted column.

- c. Save the changes.
2. Setting for assigning mail-enabled distribution groups to mailboxes.
 - The mailbox is labeled with the **Groups can be inherited** option.
 - The mailbox's Azure Active Directory user account is linked to an employee.
3. Settings for assigning mail-enabled distribution groups to mail users.
 - The mail user is labeled with the **Groups can be inherited** option.
 - The mail user is linked to an employee.
4. Settings for assigning mail-enabled distribution groups to mail contacts.
 - The mail contact is labeled with the **Groups can be inherited** option.
 - The mail contact is linked to an employee.

NOTE: There are other configuration settings that play a role when company resources are inherited through departments, cost centers, locations, and business roles. For example, role inheritance might be blocked or inheritance of employees not allowed. For more detailed information about the basic principles for assigning company resources, see the *One Identity Manager Identity Management Base Module Administration Guide*.

Related topics

- [General main data for Exchange Online mailboxes](#) on page 89
- [Main data for Exchange Online mail users](#) on page 104
- [Main data for Exchange Online mail contacts](#) on page 114

Assigning Exchange Online mail-enabled distribution groups to departments, cost centers, and locations

Assign mail-enabled distribution groups to departments, cost centers, or locations so that the mail-enabled distribution groups can be assigned to mailboxes, mail users, and mail contacts through these organizations.

To assign a mail-enabled distribution group to departments, cost centers, or locations (non role-based login)

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign organizations** task.

4. In the **Add assignments** pane, assign the organizations:

- On the **Departments** tab, assign departments.
- On the **Locations** tab, assign locations.
- On the **Cost centers** tab, assign cost centers.

TIP: In the **Remove assignments** pane, you can remove assigned organizations.

To remove an assignment

- Select the organization and double-click .


5. Save the changes.

To assign mail-enabled distribution groups to a department, a cost center, or a location (non role-based login or role-based login)

1. In the Manager, select the **Organizations > Departments** category.
- OR -
In the Manager, select the **Organizations > Cost centers** category.
- OR -
In the Manager, select the **Organizations > Locations** category.
2. Select the department, cost center or location in the result list.
3. Select the **Assign Exchange Online mail-enabled distribution list** task.
4. In the **Add assignments** pane, assign mail-enabled distribution groups.

TIP: In the **Remove assignments** pane, you can remove assigned mail-enabled distribution groups.

To remove an assignment

- Select the mail-enabled distribution group and double-click .

5. Save the changes.

Related topics

- [Prerequisites for indirect assignment of Exchange Online mail-enabled distribution groups on page 131](#)
- [Assigning Exchange Online mail-enabled distribution groups to business roles on page 134](#)
- [Adding Exchange Online mail-enabled distribution groups to system roles on page 135](#)
- [Assigning Exchange Online mail-enabled distribution groups to the IT Shop on page 136](#)
- [One Identity Manager users for managing Exchange Online on page 11](#)

Assigning Exchange Online mail-enabled distribution groups to business roles

NOTE: This function is only available if the Business Roles Module is installed.


Assign the mail-enabled distribution group to business roles so that the mail-enabled distribution group is assigned to user accounts through these business roles.

To assign a mail-enabled distribution group to business roles (non role-based login)

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign business roles** task.
4. In the **Add assignments** pane, select the role class and assign business roles.

TIP: In the **Remove assignments** pane, you can remove assigned business roles.

To remove an assignment


- Select the business role and double-click .
5. Save the changes.

To assign mail-enabled distribution groups to a business role (non role-based login or role-based login)

1. In the Manager, select the **Business roles > <role class>** category.
2. Select the business role in the result list.
3. Select the **Assign Exchange Online mail-enabled distribution list** task.
4. In the **Add assignments** pane, assign mail-enabled distribution groups.

TIP: In the **Remove assignments** pane, you can remove assigned mail-enabled distribution groups.

To remove an assignment

- Select the mail-enabled distribution group and double-click .
5. Save the changes.

Related topics

- [Prerequisites for indirect assignment of Exchange Online mail-enabled distribution groups](#) on page 131
- [Assigning Exchange Online mail-enabled distribution groups to departments, cost centers, and locations](#) on page 132

- [Adding Exchange Online mail-enabled distribution groups to system roles](#) on page 135
- [Assigning Exchange Online mail-enabled distribution groups to the IT Shop](#) on page 136
- [One Identity Manager users for managing Exchange Online](#) on page 11

Adding Exchange Online mail-enabled distribution groups to system roles

NOTE: This function is only available if the System Roles Module is installed.

Use this task to add a group to system roles. When you assign a system role to an employee, the mail-enabled distribution group are inherited by all mailboxes, mail users, and mail contacts that these employees have.


NOTE: Mail-enabled distribution groups with the **Only use in IT Shop** option set can only be assigned to system roles that also have this option set. For more information, see the *One Identity Manager System Roles Administration Guide*.

To assign an mail-enabled distribution group to system roles

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign system roles** task.
4. In the **Add assignments** pane, assign system roles.

TIP: In the **Remove assignments** pane, you can remove assigned system roles.

To remove an assignment

- Select the system role and double-click .
5. Save the changes.

Related topics

- [Assigning Exchange Online mail-enabled distribution groups to departments, cost centers, and locations](#) on page 132
- [Assigning Exchange Online mail-enabled distribution groups to business roles](#) on page 134
- [Assigning Exchange Online mail-enabled distribution groups to the IT Shop](#) on page 136

Assigning Exchange Online mail-enabled distribution groups to the IT Shop

Once a mail-enabled distribution group has been assigned to an IT Shop shelf, it can be requested by the shop customers. To ensure it can be requested, further prerequisites need to be guaranteed.

- The mail-enabled distribution group must be labeled with the **IT Shop** option.
- The mail-enabled distribution group must be assigned to a service item.

TIP: In the Web Portal, all products that can be requested are grouped together by service category. To make the mail-enabled distribution group easier to find in the Web Portal, assign a service category to the service item.

- If you want the mail-enabled distribution group to be assigned to employees only through the IT Shop, the mail-enabled distribution group must also be marked with the **Only use in IT Shop** option. Direct assignment to hierarchical roles or mailboxes, mail users and mail contacts is then no longer permitted.

NOTE: IT Shop administrators can assign mail-enabled distribution groups to IT Shop shelves in the case of role-based login. Target system administrators are not authorized to add mail-enabled distribution groups in the IT Shop.

To add a mail-enabled distribution group in the IT Shop

1. In the Manager, select the **Azure Active Directory > mail-enabled distribution groups** (non role-based login) category.
- OR -
In the Manager, select the **Entitlements > Exchange Online mail-enabled distribution groups** (role-based login) category.
2. Select the mail-enabled distribution group in the result list.
3. Select **Add to IT Shop**.
4. In the **Add assignments** pane, assign mail-enabled distribution groups to IT Shop shelves.
5. Save the changes.

To add a mail-enabled distribution group to individual IT Shop shelves

1. In the Manager, select the **Azure Active Directory > mail-enabled distribution groups** (non role-based login) category.
- OR -
In the Manager, select the **Entitlements > Exchange Online mail-enabled distribution groups** (role-based login) category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Add to IT Shop** task.

4. In the **Remove assignments** pane, removed assigned mail-enabled distribution groups from IT Shop shelves.
5. Save the changes.

To add a mail-enabled distribution group to all the IT Shop shelves

1. In the Manager, select the **Azure Active Directory > mail-enabled distribution groups** (non role-based login) category.
- OR -

In the Manager, select the **Entitlements > Exchange Online mail-enabled distribution groups** (role-based login) category.

2. Select the mail-enabled distribution group in the result list.
3. Select the **Remove from all shelves (IT Shop)** task.
4. Confirm the security prompt with **Yes**.
5. Click **OK**.

The One Identity Manager Service removes the mail-enabled distribution group from all the shelves. All requests and assignment requests with this mail-enabled distribution group are canceled at the same time.

For detailed information about requesting company resources through the IT Shop, see the *One Identity Manager IT Shop Administration Guide*.

Related topics

- [Main data for Exchange Online mail-enabled distribution groups](#) on page 124
- [Adding Exchange Online mail-enabled distribution groups automatically to the IT Shop](#) on page 137
- [Assigning Exchange Online mail-enabled distribution groups to departments, cost centers, and locations](#) on page 132
- [Assigning Exchange Online mail-enabled distribution groups to business roles](#) on page 134
- [Adding Exchange Online mail-enabled distribution groups to system roles](#) on page 135

Adding Exchange Online mail-enabled distribution groups automatically to the IT Shop

The following steps can be used to automatically add mail-enabled distribution groups to the IT Shop. Synchronization ensures that the mail-enabled distribution groups are added to the IT Shop. If necessary, you can manually start synchronization with the

Synchronization Editor. Mail-enabled distribution groups created in One Identity Manager also are added automatically to the IT Shop.

To add mail-enabled distribution groups automatically to the IT Shop

1. In the Designer, set the **QER | ITShop | AutoPublish | O3EDL** configuration parameter.
2. In order not to add mail-enabled distribution groups to the IT Shop automatically, in the Designer, set the **QER | ITShop | AutoPublish | O3EDL | ExcludeList** configuration parameter.

This configuration parameter contains a listing of all mail-enabled distribution groups that should not be allocated to the IT Shop automatically. You can extend this list if required. To do this, enter the name of the groups in the configuration parameter. Names are listed in a pipe (|) delimited list. Regular expressions are supported.

3. Compile the database.

From this time on, local mail-enabled distribution groups are added to the IT Shop automatically.

The following steps are run to add a local mail-enabled distribution group to the IT Shop automatically.

1. A service item is determined for the mail-enabled distribution group.
The service item is tested for each mail-enabled distribution group and modified if necessary. The name of the service item corresponds to the name of the mail-enabled distribution group.
 - The service item is modified if the mail-enabled distribution group has a service item.
 - Mail-enabled distribution groups without a service item are allocated a new service item.
2. The service item is assigned to the **Azure Active Directory groups | Exchange Online distribution groups** default service category.
3. An application role for product owners is determined and assigned to the service item.

Product owners can approve requests for membership in these mail-enabled distribution groups. By default, the administrator of an mail-enabled distribution group is determined to be the product owner.

NOTE: The application role for the product owner must be added under the **Request & Fulfillment | IT Shop | Product owner** application role.

- If the administrator of the mail-enabled distribution group is already a member of a product owner application role, then this application role is assigned to the service item. Therefore, all members of this application role become product owners of the mail-enabled distribution group.
- If the account manager of the mail-enabled distribution group is not yet a member of an application role for product owners, a new application role is

created. The name of the application corresponds to the name of the owner.

- If the administrator is a user account, the user account's employee is added to the application role.
 - If it is a group of administrators, the employees of all this group's user accounts are added to the application role.
4. The mail-enabled distribution group is labeled with the **IT Shop** option and assigned to the **Exchange Online distribution groups** IT Shop shelf in the **Identity & Access Lifecycle** shop.

Subsequently, the shop's customers can use the Web Portal to request memberships in the mail-enabled distribution groups.

NOTE: When a mail-enabled distribution group is irrevocably deleted from the One Identity Manager database, the associated service item is also deleted.

For more information about configuring the One Identity Manager IT Shop Administration Guide, see the *IT Shop*. For more information about requesting access requests in the Web Portal, see the *One Identity Manager Web Portal User Guide*.

Related topics

- [Assigning Exchange Online mail-enabled distribution groups to the IT Shop on page 136](#)
- [Assigning Exchange Online mail-enabled distribution groups to departments, cost centers, and locations on page 132](#)
- [Assigning Exchange Online mail-enabled distribution groups to business roles on page 134](#)
- [Adding Exchange Online mail-enabled distribution groups to system roles on page 135](#)
- [Assigning Exchange Online recipients to Exchange Online mail-enabled distribution groups on page 139](#)
- [Adding Exchange Online dynamic distribution groups to Exchange Online mail-enabled distribution groups on page 143](#)
- [Specifying Exchange Online mail-enabled distribution groups on page 129](#)

Assigning Exchange Online recipients to Exchange Online mail-enabled distribution groups

To react quickly to special requests, you can assign mail-enabled distribution groups directly to mailboxes, mail users, and mail contacts. You cannot directly assign mail-enabled distribution groups that have the **Only use in IT Shop** option set.

To assign mailboxes, mail users, and mail contacts directly to a mail-enabled distribution group

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign members** task.
4. To assign mailboxes, select the **Mailboxes** tab.

- OR -

To assign mail users, select the **Mail users** tab.


- OR -

To assign mail contacts, select the **Mail contacts** tab.

5. In the **Add assignments** pane, add the mailboxes, mail users, or mail contacts.

TIP: In the **Remove assignments** pane, you can remove mailboxes, mail users, and mail contacts.

To remove an assignment

- Select the mailbox, mail user, or mail contact and double-click .

6. Save the changes.

Related topics


- [Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mailboxes on page 140](#)
- [Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mail users on page 141](#)
- [Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mail contacts on page 142](#)

Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mailboxes

To react quickly to special requests, you can assign mail-enabled distribution groups directly to mailboxes.

To assign mail-enabled distribution groups to a mailbox

1. In the Manager, select the **Azure Active Directory > Mailboxes** category.
2. Select a mailbox in the result list.

3. Select the **Assign mail-enabled distribution list** task.
4. In the **Add assignments** pane, assign mail-enabled distribution groups.
TIP: In the **Remove assignments** pane, you can remove assigned mail-enabled distribution groups.
To remove an assignment
 - Select the mail-enabled distribution group and double-click .
5. Save the changes.


Related topics

- [Assigning Exchange Online recipients to Exchange Online mail-enabled distribution groups](#) on page 139

Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mail users

To react quickly to special requests, you can assign mail-enabled distribution groups directly to mail users.

To assign mail-enabled distribution groups directly to a mail user

1. In the Manager, select the **Azure Active Directory > Mail users** category.
2. Select the mail user in the result list.
3. Select the **Assign mail-enabled distribution list** task.
4. In the **Add assignments** pane, assign mail-enabled distribution groups.
TIP: In the **Remove assignments** pane, you can remove assigned mail-enabled distribution groups.
To remove an assignment
 - Select the mail-enabled distribution group and double-click .
5. Save the changes.

Related topics

- [Assigning Exchange Online recipients to Exchange Online mail-enabled distribution groups](#) on page 139

Assigning Exchange Online mail-enabled distribution groups directly to Exchange Online mail contacts


To react quickly to special requests, you can assign mail-enabled distribution groups directly to mail contacts.

To assign mail-enabled distribution groups directly to a mail contact

1. In the Manager, select the **Azure Active Directory > Mail contacts** category.
2. Select the mail contact in the result list.
3. Select the **Assign mail-enabled distribution list** task.
4. In the **Add assignments** pane, assign mail-enabled distribution groups.

TIP: In the **Remove assignments** pane, you can remove assigned mail-enabled distribution groups.

To remove an assignment

- Select the mail-enabled distribution group and double-click .
5. Save the changes.

Related topics

- [Assigning Exchange Online recipients to Exchange Online mail-enabled distribution groups](#) on page 139

Exchange Online mail-enabled distribution group inheritance based on categories

In Exchange Online, mail-enabled distribution groups can be inherited by mailboxes, mail users, and mail contacts through categories.

For more information, see the *One Identity Manager Administration Guide for Connecting to Azure Active Directory*.

To use inheritance through categories

1. In the Manager, define the categories in the Azure Active Directory tenant.

To edit Azure Active Directory tenant main data

- a. In the Manager, select the **Azure Active Directory > Tenants** category.
 - b. In the result list, select the Azure Active Directory tenant.
 - c. Select the **Change main data** task.
 - d. Edit the Azure Active Directory tenant's main data.
 - e. Save the changes.
2. In the Manager, assign categories to mailboxes, mail users, and mail contacts through their main data.
 3. In the Manager, assign categories to mail-enabled distribution groups through their main data.

Related topics

- [General main data for Exchange Online mailboxes](#) on page 89
- [Main data for Exchange Online mail users](#) on page 104
- [Main data for Exchange Online mail contacts](#) on page 114
- [Main data for Exchange Online mail-enabled distribution groups](#) on page 124


Adding Exchange Online dynamic distribution groups to Exchange Online mail-enabled distribution groups

To add dynamic distribution groups to a mail-enabled distribution group

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign mail-enabled distribution list** task.
4. In the **Add assignments** pane, assign mail-enabled distribution groups.

TIP: In the **Remove assignments** pane, you can remove assigned mail-enabled distribution groups.

To remove an assignment

- Select the mail-enabled distribution group and double-click .
5. Save the changes.


Adding an Exchange Online dynamic distribution group to Exchange Online mail-enabled distribution groups

To add dynamic distribution groups to a mail-enabled distribution group

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign members** task.
4. Select the **Dynamic distribution groups** tab.
5. In the **Add assignments** pane, assign dynamic distribution groups.

TIP: In the **Remove assignments** pane, you can remove assigned dynamic mail-enabled distribution groups.

To remove an assignment

- Select the dynamic mail-enabled distribution group and double-click .
6. Save the changes.

Related topics

- [Adding Exchange Online mail-enabled distribution groups to Exchange Online dynamic distribution groups](#) on page 173


Adding Exchange Online mail-enabled public folder to Exchange Online mail-enabled distribution groups

To add mail-enabled public folders to a mail-enabled distribution group

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign mail-enabled public folder** task.
4. In the **Add assignments** pane, assign mail-enabled public folders.

TIP: In the **Remove assignments** pane, you can remove assigned mail-enabled public folders.

To remove an assignment

- Select the mail-enabled public folder and click .
5. Save the changes.

Assigning extended properties to Exchange Online mail-enabled distribution groups

Extended properties are meta objects, such as operating codes, cost codes, or cost accounting areas that cannot be mapped directly in One Identity Manager.


For more information about using extended properties, see the *One Identity Manager Identity Management Base Module Administration Guide*.

To specify extended properties for mail-enabled distribution groups

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.
3. Select **Assign extended properties**.
4. In the **Add assignments** pane, assign extended properties.

TIP: In the **Remove assignments** pane, you can remove assigned extended properties.

To remove an assignment


- Select the extended property and double-click .
5. Save the changes.

Deleting Exchange Online mail-enabled distribution groups

When you delete a mail-enabled distribution group, the Azure Active Directory group associated with the mail-enabled distribution group is also deleted.

To delete a mail-enabled distribution group

1. In the Manager, select the **Azure Active Directory > Mail-enabled distribution groups** category.
2. Select the mail-enabled distribution group in the result list.

3. Click  in the result list.
4. Confirm the security prompt with **Yes**.

Exchange Online Office 365 groups

Office 365 groups are loaded into One Identity Manager by synchronization. You can create and edit Office 365 groups in One Identity Manager. When you create an Office 365 group, an Azure Active Directory group is also created and linked to the Office 365 group.

In One Identity Manager, you can assign Office 365 groups directly to mailboxes, mail users, and mail contacts or they can be inherited through departments, cost centers, locations, or business roles. Users can also request Office 365 groups through the Web Portal. To do this, Office 365 groups are supplied by the IT Shop.


Detailed information about this topic

- [Creating Exchange Online Office 365 groups](#) on page 147
- [Editing main data of Exchange Online Office 365 groups](#) on page 148
- [Exchange Online Office 365 group main data](#) on page 148
- [Customizing receive restrictions for Exchange Online Office 365 groups](#) on page 152
- [Assigning owners to Exchange Online Office 365 groups](#) on page 153
- [Assigning subscribers to Exchange Online Office 365 groups](#) on page 154
- [Assigning Exchange Online Office 365 groups to Azure Active Directory user accounts](#) on page 154
- [Exchange Online Office 365 group inheritance based on categories](#) on page 165
- [Assigning extended properties to Exchange Online Office 365 groups](#) on page 166
- [Deleting Exchange Online Office 365 groups](#) on page 167
- [Synchronizing single objects](#) on page 46

Creating Exchange Online Office 365 groups

When you create an Office 365 group, an Azure Active Directory group is also created and linked to the Office 365 group.

To create a Office 365 group

1. In the Manager, select the **Azure Active Directory > Office 365 groups** category.
2. Click  in the result list.
3. On the main data form, enter the main data for the Office 365 group.
4. Save the changes.

Related topics

- [Editing main data of Exchange Online Office 365 groups](#) on page 148
- [Exchange Online Office 365 group main data](#) on page 148

Editing main data of Exchange Online Office 365 groups

To edit an Office 365 group

1. In the Manager, select the **Azure Active Directory > Office 365 groups** category.
2. Select the Office 365 group in the result list and run the **Change main data** task.
3. Edit the Office 365 group's main data.
4. Save the changes.

Related topics

- [Creating Exchange Online Office 365 groups](#) on page 147
- [Exchange Online Office 365 group main data](#) on page 148

Exchange Online Office 365 group main data

Table 20: Exchange Online group main data

Property	Description
Azure Active Directory tenant	The Azure Active Directory tenant's name.

Property	Description
Name	Name of the Office 365 group.
Display name	Name as used in the address book.
Simple display	Simple display name for systems that cannot interpret all the characters of normal display names.
Alias	Unique alias for further identification of the Office 365 group.
Group type	The type of group.
Proxy addresses	Office 365 group's email addresses You can also add other mail connectors (for example, CCMail, MS) in addition to the standard address type (SMTP, X400). Use the following syntax to set up other proxy addresses: Address type: new email address
Yammer email address	Yammer email address.
Notes	More information about the Office 365 group.
Azure Active Directory group	Azure Active Directory group for which an Office 365 group is created.
IT Shop	Specifies whether the group can be requested through the IT Shop. If this option is set, the group can be requested by the employees through the Web Portal and distributed with a defined approval process. The group can still be assigned directly to mailboxes, mail users and mail contacts, and to hierarchical roles.
Only for use in IT Shop	Specifies whether the group can only be requested through the IT Shop. If this option is set, the group can be requested by the employees through the Web Portal and distributed with a defined approval process. Direct assignment of the group to hierarchical roles or mailboxes, mail users and mail contacts is not permitted.
Service item	Service item data for requesting the group through the IT Shop.
Risk index	Value for assessing the risk of assigning the group to mailboxes, mail users and mail contacts. Set a value in the range 0 to 1 . This field is only visible if the QER CalculateRiskIndex configuration parameter is set. For more information about risk assessment, see the <i>One Identity Manager Risk Assessment Administration Guide</i> .
Category	Categories used by mailboxes, mail users and mail contacts to inherit groups. Groups can be selectively inherited by mailboxes, mail users and mail contacts. To do this, the group and mailboxes, mail users and mail contacts are divided into categories. Select one or more categories from

Property	Description
	the menu.
Privacy	Privacy type for Office 365 groups. Options are Private (default) or Public .
Language	Language of the Office 365 group.
Do not display in address list	Specifies whether the Office 365 group is visible in address books. Set this option if you want to prevent the Office 365 group from being displayed in address books. This option applies to all address books.
Hide group memberships	Specifies whether to hide the members of the Office 365 group from users who are not members of the group. This option can only be enabled for private groups.
Hide group in Outlook	Specifies whether the Office 365 group is shown in Outlook. Set this option if you want to prevent the Office 365 group from being displayed in Outlook. The Office 365 groups is also hidden in address books.
Exchange version	Specifies the version of Exchange.
Mailbox configured	Specifies whether a mailbox is configured for the Office 365 group.
Inbox URL	URL of the inbox.
Max. send size [KB]	Maximum size of outgoing messages in KB.
Sender authentication required	Specifies whether authentication data is requested from senders. Set this option to prevent anonymous senders mailing the Office 365 group.
Mailbox provisioning constraint	Additional options for mailbox provisioning.
MailTip	Specifies the custom MailTip text for this recipient.
MailTip translations	Languages for the custom MailTip text.
Welcome message enabled	Specifies whether the welcome message is sent.
Migration to Office 365 group in progress	Specifies the migration status.

Property	Description
Valid	Specifies whether this Office 365 group is valid.
Dynamic membership	Specifies whether memberships are dynamic memberships.
Allow adding of new guests	Specifies whether new guests can be added to the Office 365 group.
External members count	Number of external group members.
Allow subscriptions	Specifies whether subscriptions to conversations and calendar events are enabled for the Office 365 group. Use the Assign subscriptions task to assign subscribers.
Automatically subscribe new members	Specifies whether to automatically subscribe new members of the Office 365 group to conversations and calendar events.
Always subscribe members to calendar events	Specifies whether to subscribe members of the Office 365 group only to group calendar events, and not conversations.
External resources published	Specifies whether external resources are published.
Connectors enabled	Specifies whether to enable the use of connectors for apps, tools, or services for the Office 365 group.
Synchronized with local Active Directory	Specifies whether the group has been synchronized with the local Active Directory and with Exchange Online.
File notification settings	Settings for file notification.
Employee URL	Employee's URL.
Photo URL	Photo URL.
SharePoint documents URL	URL of the SharePoint documents.

Property	Description
SharePoint notebook URL	URL of the SharePoint notebook.
SharePoint site URL	URL of the SharePoint site.
Custom attribute 01 - Custom attribute 15	Additional company-specific information. Use the Designer to customize display names, formats, and templates for the input fields.
Attribute extension 01 - attribute extension 15	Additional company-specific information. Use the Designer to customize display names, formats, and templates for the input fields.

Related topics


- [Assigning subscribers to Exchange Online Office 365 groups](#) on page 154

Customizing receive restrictions for Exchange Online Office 365 groups

NOTE: The **Assign mail acceptance** and **Assign mail rejection** assignments are mutually exclusive. You can specify whether to accept or deny the recipient's message.

To customize mail acceptance for Office 365 mailboxes groups

1. In the Manager, select the **Azure Active Directory > Office 365 groups** category.
2. Select the Office 365 group in the result list.
3. Select the **Assign mail acceptance** task to specify recipients whose messages are accepted.
- OR -
Select the **Assign mail rejection** task to specify recipients whose messages are rejected.
4. Select the table containing the recipient from the menu at the top of the form. You have the following options:
 - Mail-enabled distribution groups
 - Dynamic distribution groups
 - Mailboxes

- Mail users
 - Mail contacts
 - Office 365 groups
5. In the **Add assignments** pane, assign recipients.
TIP: In the **Remove assignments** pane, you can remove assigned recipients.
To remove an assignment
 - Select the recipient and double-click .
 6. Save the changes.

Assigning owners to Exchange Online Office 365 groups

When you assign owners to an Office 365 group, the owners are also added as members to the Office 365 group.


NOTE: Owners cannot be manually assigned to Office 365 groups.

To assign owners to an Office 365 group

1. In the Manager, select the **Azure Active Directory > Office 365 groups** category.
2. Select the Office 365 group in the result list.
3. Select the **Assign owners** task.
4. In the **Add assignments** pane, assign owners.

TIP: In the **Remove assignments** pane, you can remove assigned owners.

To remove an assignment

- Select the owner and double-click .
5. Save the changes.

Related topics

- [Assigning Azure Active Directory user accounts directly to Exchange Online Office 365 groups on page 164](#)

Assigning subscribers to Exchange Online Office 365 groups

You can assign subscribers to Office 365 groups if the **Allow subscriptions** option is set. If you assign subscribers to an Office 365 group, the subscribers are also added as members to the Office 365 group.


NOTE: Subscribers cannot be manually assigned to dynamic Office 365 groups.

To assign subscribers to an Office 365 group

1. In the Manager, select the **Azure Active Directory > Office 365 groups** category.
2. Select the Office 365 group in the result list.
3. Select the **Assign subscribers** task.
4. In the **Add assignments** pane, add subscribers.

TIP: In the **Remove assignments** pane, you can remove assigned subscribers.

To remove an assignment

- Select the subscriber and double-click .
5. Save the changes.

Related topics

- [Exchange Online Office 365 group main data](#) on page 148
- [Editing main data of Exchange Online Office 365 groups](#) on page 148
- [Assigning Azure Active Directory user accounts directly to Exchange Online Office 365 groups](#) on page 164

Assigning Exchange Online Office 365 groups to Azure Active Directory user accounts

Office 365 groups can be assigned directly or indirectly to Azure Active Directory user accounts.

In the case of indirect assignment, employees and Office 365 groups are assigned to hierarchical roles, such as departments, cost centers, locations, or business roles. The Office 365 groups assigned to an employee are calculated from the position in the hierarchy and the direction of inheritance. If you add an employee to roles and that

employee owns an Azure Active Directory user account, the Azure Active Directory user account is added to the Office 365 group.

Furthermore, Office 365 groups can be requested through the Web Portal. To do this, add employees to a shop as customers. All Office 365 groups are assigned to this shop can be requested by the customers. Requested Office 365 groups are assigned to the employees after approval is granted.

Through system roles, Office 365 groups can be grouped together and assigned to employees and workdesks as a package. You can create system roles that contain only Office 365 groups. You can also group any number of company resources into a system role.

To react quickly to special requests, you can assign Office 365 groups directly to Azure Active Directory user accounts.

For detailed information see the following guides:

Topic	Guide
Basic principles for assigning and inheriting company resources	<i>One Identity Manager Identity Management Base Module Administration Guide</i> <i>One Identity Manager Business Roles Administration Guide</i>
Assigning company resources through IT Shop requests	<i>One Identity Manager IT Shop Administration Guide</i>
System roles	<i>One Identity Manager System Roles Administration Guide</i>

Detailed information about this topic

- [Prerequisites for indirect assignment of Office 365 groups to Azure Active Directory user accounts on page 156](#)
- [Assigning Exchange Online Office 365 groups to departments, cost centers, and locations on page 157](#)
- [Assigning Exchange Online Office 365 groups to business roles on page 158](#)
- [Adding Exchange Online Office 365 groups to system roles on page 159](#)
- [Adding Exchange Online Office 365 groups to the IT Shop on page 160](#)
- [Anwendungsrolle für Produkteigner ermittelt und Adding Exchange Online Office 365 groups automatically to the IT Shop on page 162](#)
- [Assigning Azure Active Directory user accounts directly to Exchange Online Office 365 groups on page 164](#)
- [Assigning Exchange Online Office 365 groups directly to Azure Active Directory user accounts on page 164](#)

Prerequisites for indirect assignment of Office 365 groups to Azure Active Directory user accounts

In the case of indirect assignment, employees and Office 365 groups are assigned to hierarchical roles, such as departments, cost centers, locations, or business roles. When assigning Office 365 groups indirectly, check the following settings and modify them if necessary.

1. Assignment of employees and Exchange Online Office 365 groups is permitted for role classes (departments, cost centers, locations, or business roles).

For more information, see the *One Identity Manager Identity Management Base Module Administration Guide*.

To configure assignments to roles of a role class

- a. In the Manager, select role classes in the **Organizations > Basic configuration data > Role classes** category.
- OR -
In the Manager, select role classes in the **Business roles > Basic configuration data > Role classes** category.
- b. Select the **Configure role assignments** task and configure the permitted assignments.
 - To generally allow an assignment, enable the **Assignments allowed** column.
 - To allow direct assignment, enable the **Direct assignments permitted** column.
- c. Save the changes.

2. Settings for assigning Office 365 groups to Azure Active Directory user accounts.

- The Azure Active Directory user account is linked to an employee.
- The Azure Active Directory user account has the **Office 365 groups can be inherited** option set.

The option specifies whether the Azure Active Directory user account can inherit Office 365 groups through the linked employee. If the option is set, the user account inherits Office 365 groups through hierarchical roles, in which the employee is a member, or through IT Shop requests.

- If you add an employee with a user account to a department, for example, and you have assigned Office 365 groups to this department, the Azure Active Directory user account inherits these Office 365 groups.
- If an employee has requested group membership in the IT Shop and the

request is granted approval, the employee's Azure Active Directory user account only inherits the Office 365 group if the option is set.

To edit main data of a user account

- a. In the Manager, select the **Azure Active Directory > User accounts** category.
- b. Select the user account in the result list.
- c. Select the **Change main data** task.
- d. Edit the user account's resource data.
- e. Save the changes.

For more information about Azure Active Directory user accounts, see the *One Identity Manager Administration Guide for Connecting to Azure Active Directory*.

NOTE: There are other configuration settings that play a role when company resources are inherited through departments, cost centers, locations, and business roles. For example, role inheritance might be blocked or inheritance of employees not allowed. For more detailed information about the basic principles for assigning company resources, see the *One Identity Manager Identity Management Base Module Administration Guide*.

Assigning Exchange Online Office 365 groups to departments, cost centers, and locations

Assign groups to departments, cost centers, or locations so that the group can be assigned to user accounts through these organizations.

To assign a group to departments, cost centers, or locations (non role-based login)

1. In the Manager, select the **Azure Active Directory > Office 365 groups** category.
2. Select the group in the result list.
3. Select the **Assign organizations** task.
4. In the **Add assignments** pane, assign the organizations:
 - On the **Departments** tab, assign departments.
 - On the **Locations** tab, assign locations.
 - On the **Cost centers** tab, assign cost centers.

TIP: In the **Remove assignments** pane, you can remove assigned organizations.

To remove an assignment

- Select the organization and double-click ✓.
5. Save the changes.

To assign groups to a department, a cost center, or a location (non role-based login or role-based login)

1. In the Manager, select the **Organizations > Departments** category.
- OR -
In the Manager, select the **Organizations > Cost centers** category.
- OR -
In the Manager, select the **Organizations > Locations** category.
2. Select the department, cost center, or location in the result list.
3. Select the **Assign Office 365 groups** task.
4. In the **Add assignments** pane, assign groups.

TIP: In the **Remove assignments** pane, you can remove the assignment of groups.

To remove an assignment

- Select the group and double-click ✓.
5. Save the changes.

Related topics

- [Prerequisites for indirect assignment of Office 365 groups to Azure Active Directory user accounts](#) on page 156
- [Assigning Exchange Online Office 365 groups to business roles](#) on page 158
- [Adding Exchange Online Office 365 groups to system roles](#) on page 159
- [Adding Exchange Online Office 365 groups to the IT Shop](#) on page 160
- [One Identity Manager users for managing Exchange Online](#) on page 11

Assigning Exchange Online Office 365 groups to business roles

NOTE: This function is only available if the Business Roles Module is installed.


Assign the group to business roles so that the group is assigned to user accounts through these business roles.

To assign a group to a business role (non role-based login)

1. In the Manager, select the **Azure Active Directory > Office 365 groups** category.
2. Select the group in the result list.
3. Select the **Assign business roles** task.
4. In the **Add assignments** pane, select the role class and assign business roles.

TIP: In the **Remove assignments** pane, you can remove assigned business roles.

To remove an assignment


- Select the business role and double-click .
5. Save the changes.

To assign groups to a business role (non role-based login or role-based login)

1. In the Manager, select the **Business roles > <role class>** category.
2. Select the business role in the result list.
3. Select the **Assign Office 365 groups** task.
4. In the **Add assignments** pane, assign the groups.

TIP: In the **Remove assignments** pane, you can remove the assignment of groups.

To remove an assignment

- Select the group and double-click .
5. Save the changes.

Related topics

- [Prerequisites for indirect assignment of Office 365 groups to Azure Active Directory user accounts](#) on page 156
- [Assigning Exchange Online Office 365 groups to departments, cost centers, and locations](#) on page 157
- [Adding Exchange Online Office 365 groups to system roles](#) on page 159
- [Adding Exchange Online Office 365 groups to the IT Shop](#) on page 160
- [One Identity Manager users for managing Exchange Online](#) on page 11

Adding Exchange Online Office 365 groups to system roles

| NOTE: This function is only available if the System Roles Module is installed.

Use this task to add a group to system roles.

If you assign a system role to employees, all Azure Active Directory user accounts owned by this employee inherit the group.

This task is not available for dynamic groups.


NOTE: Groups with **Only use in IT Shop** set can only be assigned to system roles that also have this option set. For more information, see the *One Identity Manager System Roles Administration Guide*.

To assign a group to system roles

1. In the Manager, select the **Azure Active Directory > Office 365 groups** category.
2. Select the group in the result list.
3. Select the **Assign system roles** task.
4. In the **Add assignments** pane, assign system roles.

TIP: In the **Remove assignments** pane, you can remove assigned system roles.

To remove an assignment

- Select the system role and double-click .
5. Save the changes.

Related topics

- [Prerequisites for indirect assignment of Office 365 groups to Azure Active Directory user accounts](#) on page 156
- [Assigning Exchange Online Office 365 groups to departments, cost centers, and locations](#) on page 157
- [Assigning Exchange Online Office 365 groups to business roles](#) on page 158
- [Adding Exchange Online Office 365 groups to the IT Shop](#) on page 160

Adding Exchange Online Office 365 groups to the IT Shop

When an Office 365 group is assigned to an IT Shop shelf, the Office 365 group can be requested by the customers of the shop. To ensure it can be requested, further prerequisites need to be guaranteed.

- The group is not a dynamic group.
- The Office 365 group must be labeled with the **IT Shop** option.
- The Office 365 group must be assigned to a service item.

TIP: In the Web Portal, all products that can be requested are grouped together by service category. To make the Web Portal group easier to find in the Office 365,

| assign a service category to the service item.

- If you want the Office 365 group to be assigned only to employees through the IT Shop, the Office 365 group must also be marked with the **Only use in IT Shop** option. Direct assignment to hierarchical roles or Active Directory user accounts is then no longer permitted.

NOTE: IT Shop administrators can assign Office 365 groups to the IT Shop shelves if login is role-based. Target system administrators are not authorized to add Office 365 groups in the IT Shop.

To add a Office 365 group to the IT Shop

1. In the Manager, select the **Azure Active Directory > Office 365 Groups** (non role-based login) category.
- OR -
In the Manager, select the **Entitlements > Office 365 groups** (role-based login) category.
2. Select the Office 365 group in the result list.
3. Select **Add to IT Shop**.
4. In the **Add assignments** pane, assign the Office 365 group to the IT Shop shelves.
5. Save the changes.

To remove an Office 365 group from individual IT Shop shelves

1. In the Manager, select the **Azure Active Directory > Office 365 Groups** (non role-based login) category.
- OR -
In the Manager, select the **Entitlements > Office 365 groups** (role-based login) category.
2. Select the Office 365 group in the result list.
3. Select **Add to IT Shop**.
4. In the **Remove assignments** pane, remove the Office 365 group from the IT Shop shelves.
5. Save the changes.

To remove an Office 365 group from all IT Shop shelves

1. In the Manager, select the **Azure Active Directory > Office 365 Groups** (non role-based login) category.
- OR -
In the Manager, select the **Entitlements > Office 365 groups** (role-based login) category.
2. Select the Office 365 group in the result list.
3. Select the **Remove from all shelves (IT Shop)** task.

4. Confirm the security prompt with **Yes**.
5. Click **OK**.

The Office 365 group is removed from all shelves by the One Identity Manager Service. All requests and assignment requests with this Office 365 group are canceled in the process.

For detailed information about requesting company resources through the IT Shop, see the *One Identity Manager IT Shop Administration Guide*.

Related topics

- [Exchange Online Office 365 group main data](#) on page 148
- [Prerequisites for indirect assignment of Office 365 groups to Azure Active Directory user accounts](#) on page 156
- [Anwendungsrolle für Produkteigner ermittelt und Adding Exchange Online Office 365 groups automatically to the IT Shop](#) on page 162
- [Assigning Exchange Online Office 365 groups to departments, cost centers, and locations](#) on page 157
- [Assigning Exchange Online Office 365 groups to business roles](#) on page 158
- [Adding Exchange Online Office 365 groups to system roles](#) on page 159

Anwendungsrolle für Produkteigner ermittelt und Adding Exchange Online Office 365 groups automatically to the IT Shop

The following steps can be used to automatically add Exchange Online Office 365 teams to the IT Shop. Synchronization ensures that the Office 365 groups are added to the IT Shop. If necessary, you can manually start synchronization with the Synchronization Editor. New Office 365 groups created in One Identity Manager also are added automatically to the IT Shop.

To add Office 365 groups automatically to the IT Shop

1. In the Designer, set the **QER | ITShop | AutoPublish | O3EUnifiedGroup** configuration parameter.
2. In order not to add Office 365 groups to the IT Shop automatically, in the Designer, set the **QER | ITShop | AutoPublish | O3EUnifiedGroup | ExcludeList** configuration parameter.

This configuration parameter contains a listing of all Office 365 groups that should not be allocated to the IT Shop automatically. You can extend this list if required. To do this, enter the name of the groups in the configuration parameter. Names are listed in a pipe (|) delimited list. Regular expressions are supported.

3. Compile the database.

The Office 365 groups are added automatically to the IT Shop from now on.

The following steps are run to add a Office 365 group to the IT Shop.

1. A service item is determined for the Office 365 group.

The service item is tested for each Office 365 group and modified if necessary. The name of the service item corresponds to the name of the Office 365 group.

- The service item is modified for Office 365 groups with service items.
- Office 365 groups without service items are allocated new service items.

2. The service item is assigned to the **Azure Active Directory groups | Office 365 groups** default service category.

3. An application role for product owners is determined and assigned to the service item.

Product owners can approve requests for membership in these Office 365 groups. The default product owner is the Office 365 group's owner.

NOTE: The application role for the product owner must be added under the **Request & Fulfillment | IT Shop | Product owner** application role.

- If the owner of the Office 365 group is already a member of an application role for product owners, this application role is assigned to the service item. Therefore, all members of this application role become product owners of the Azure Active Directory group.
- If the owner of the Office 365 group is not yet a member of an application role for product owners, a new application role is created. The name of the application corresponds to the name of the owner.
 - If the owner is a user account, the user account's employee is added to the application role.
 - If it is a group of owners, the employees of all this group's user accounts are added to the application role.

4. The Office 365 group is labeled with the **IT Shop** option and assigned to the **Office 365 groups** IT Shop shelf in the **Identity & Access Lifecycle** shop.

Then the shop customers can use the Web Portal to request memberships in Office 365 groups.

NOTE: If an Office 365 group is irrevocably deleted from the One Identity Manager database, the associated service item is also deleted.

For more information about configuring the One Identity Manager IT Shop Administration Guide, see the *IT Shop*. For more information about requesting access requests in the Web Portal, see the *One Identity Manager Web Portal User Guide*.

Related topics

- [Adding Exchange Online Office 365 groups to the IT Shop](#) on page 160
- [Assigning Exchange Online Office 365 groups to departments, cost centers, and locations](#) on page 157

- [Assigning Exchange Online Office 365 groups to business roles](#) on page 158
- [Adding Exchange Online Office 365 groups to system roles](#) on page 159
- [Assigning Azure Active Directory user accounts directly to Exchange Online Office 365 groups](#) on page 164

Assigning Exchange Online Office 365 groups directly to Azure Active Directory user accounts


To react quickly to special requests, you can assign groups directly to the user account. You cannot directly assign groups that have the **Only use in IT Shop** option set.

To assign groups directly to user accounts

1. In the Manager, select the **Azure Active Directory > User accounts** category.
2. Select the user account in the result list.
3. Select the **Assign Office 365 groups** task.
4. In the **Add assignments** pane, assign the groups.

TIP: In the **Remove assignments** pane, you can remove the assignment of groups.

To remove an assignment

- Select the group and double-click .
5. Save the changes.

Related topics

- [Assigning Azure Active Directory user accounts directly to Exchange Online Office 365 groups](#) on page 164

Assigning Azure Active Directory user accounts directly to Exchange Online Office 365 groups

To react quickly to special requests, you can assign groups directly to user accounts. You cannot directly assign groups that have the **Only use in IT Shop** option set.

If you assign owners and subscribers to an Office 365 group, the user accounts are also added as members to the Office 365 group.


NOTE: User accounts cannot be manually added to dynamic Office 365 groups.

To assign user accounts directly to a group

1. In the Manager, select the **Azure Active Directory > Office 365 groups** category.
2. Select the Office 365 group in the result list.
3. Select the **Assign members** task.
4. In the **Add assignments** pane, assign the user accounts.

TIP: In the **Remove assignments** pane, you can remove assigned user accounts.

To remove an assignment

- Select the user account and double-click .
5. Save the changes.

Related topics

- [Assigning Exchange Online Office 365 groups directly to Azure Active Directory user accounts](#) on page 164
- [Assigning owners to Exchange Online Office 365 groups](#) on page 153
- [Assigning subscribers to Exchange Online Office 365 groups](#) on page 154

Exchange Online Office 365 group inheritance based on categories

In Exchange Online, Office 365 groups can be inherited by Azure Active Directory user accounts through categories.

For more information, see the *One Identity Manager Administration Guide for Connecting to Azure Active Directory*.

To use inheritance through categories

1. In the Manager, define the categories in the Azure Active Directory tenant.

To edit Azure Active Directory tenant main data

- a. In the Manager, select the **Azure Active Directory > Tenants** category.
- b. In the result list, select the Azure Active Directory tenant.
- c. Select the **Change main data** task.
- d. Edit the Azure Active Directory tenant's main data.
- e. Save the changes.

2. In the Manager, assign categories to Azure Active Directory user accounts through their main data.

To edit main data of a user account

- a. In the Manager, select the **Azure Active Directory > User accounts** category.
 - b. Select the user account in the result list.
 - c. Select the **Change main data** task.
 - d. Edit the user account's resource data.
 - e. Save the changes.
3. In the Manager, assign categories to Office 365 groups through their main data.

Related topics

- [Exchange Online Office 365 group main data](#) on page 148

Assigning extended properties to Exchange Online Office 365 groups

Extended properties are meta objects, such as operating codes, cost codes, or cost accounting areas that cannot be mapped directly in One Identity Manager.


For more information about using extended properties, see the *One Identity Manager Identity Management Base Module Administration Guide*.

To specify extended properties for an Office 365 group

1. In the Manager, select the **Azure Active Directory > Office 365 groups** category.
2. Select the Office 365 group in the result list.
3. Select **Assign extended properties**.
4. In the **Add assignments** pane, assign extended properties.

TIP: In the **Remove assignments** pane, you can remove assigned extended properties.


To remove an assignment

- Select the extended property and double-click .
5. Save the changes.

Deleting Exchange Online Office 365 groups

When you delete an Office 365 group, the Azure Active Directory group associated with the Office 365 group is also deleted.

To delete an Office 365 group

1. In the Manager, select the **Azure Active Directory > Office 365 groups** category.
2. Select the Office 365 group in the result list.
3. Click  in the result list.
4. Confirm the security prompt with **Yes**.

Exchange Online dynamic distribution groups

The members of a dynamic distribution group are not fixed but are determined using a filter criteria. Dynamic distribution groups are loaded into One Identity Manager through synchronization and can only be edited to a limited extent in One Identity Manager. You cannot create new dynamic distribution groups in One Identity Manager.

Detailed information about this topic

- [Editing main data of Exchange Online dynamic distribution groups](#) on page 168
- [Main data for Exchange Online dynamic distribution groups](#) on page 169
- [Customizing receive restrictions for Exchange Online dynamic distribution groups](#) on page 171
- [Customizing send permissions for Exchange Online dynamic distribution groups](#) on page 172
- [Specifying moderators for Exchange Online dynamic distribution groups](#) on page 172
- [Adding Exchange Online mail-enabled distribution groups to Exchange Online dynamic distribution groups](#) on page 173
- [Deleting Exchange Online dynamic distribution groups](#) on page 174
- [Synchronizing single objects](#) on page 46

Editing main data of Exchange Online dynamic distribution groups

To edit the main data of a dynamic distribution group

1. In the Manager, select the **Azure Active Directory > Tenants > <Azure Active Directory tenant> > Exchange Online administration > Recipient configuration > Dynamic distribution groups** category.

2. Select the dynamic distribution group in the result list and run the **Change main data** task.
3. Edit the dynamic distribution group's main data.
4. Save the changes.

Related topics

- [Main data for Exchange Online dynamic distribution groups](#) on page 169

Main data for Exchange Online dynamic distribution groups

Table 21: Dynamic distribution list main data

Property	Description
Azure Active Directory tenant	The Azure Active Directory tenant's name.
Identifier	Unique name of the dynamic distribution group.
Name	Name of the dynamic distribution group.
Alias	Unique alias for further identification of the dynamic distribution group.
Display name	Name as used in the address book.
Simple display	Simple display name for systems that cannot interpret all the characters of normal display names.
Phonetic display name	Specifies an alternative way of writing the name that is used in text-to-speech in Unified Messaging (UM). For example, it is used if the pronunciation and spelling of the name do not match.
Proxy addresses	Other email addresses for the dynamic distribution group.
Email address	Email addresses of the dynamic distribution group.
Do not display in address list	Specifies whether the dynamic distribution group is visible in address books. Set this option if you want to prevent the dynamic distribution group from being displayed in address books. This option applies to all address books.
Recipient container	Recipient's root container. The condition for finding distribution group members is applied to the selected recipient container and its sub containers.

Property	Description
Recipient filter type	Type filter for the recipient.
Included recipients	Prescanned filter forms the basis of the recipient type. Permitted values are AllRecipient , Resources , MailUsers , MailboxUsers , MailContacts , and MailGroups . You can combine several recipient type in a comma delimited list.
Recipient filter	Condition with extra filter criteria, which is used to determine the members of the dynamic distribution group
Filter rules	Filter rules for finding members in the dynamic distribution group.
Administrator	Administrator for the dynamic distribution group. To specify an administrator <ol style="list-style-type: none"> 1. Click ➔ next to the field. 2. In the Table menu, select the table that maps the account manager. 3. Under Administrators, select the administrators. 4. Click OK.
Notes	Additional information about the dynamic distribution group.
Report to sender	Specifies whether the delivery reports are sent to the message sender.
Report to owner	Specifies whether the delivery reports are sent to the message owner.
Moderation enabled	Specifies whether the mail user is moderated. Use the Assign moderators task to specify the moderators. Then enable the option.
Sending message	Specifies how senders are notified when they send messages to moderated dynamic distribution groups. Permitted values are: <ul style="list-style-type: none"> • Do not notify: The sender is not notified. • Only notify senders in your exchange organization: Only internal senders receive a notification. • Notify all senders: Internal and external senders receive notification.
Out-of-office message to sender	Specifies whether the message sender should receive out-of-office messages.
Only limit messages from authenticated users	Specifies whether authentication data is requested from senders.

Related topics

- [Specifying moderators for Exchange Online dynamic distribution groups](#) on page 172

Customizing receive restrictions for Exchange Online dynamic distribution groups

NOTE: The **Assign mail acceptance** and **Assign mail rejection** assignments are mutually exclusive. You can specify whether to accept or deny the recipient's message.

To modify mail acceptance for dynamic distribution groups

1. In the Manager, select the **Azure Active Directory > Tenants > <Azure Active Directory tenant> > Exchange Online administration > Recipient configuration > Dynamic distribution groups** category.
2. Select the dynamic distribution list in the result list.
3. Select the **Assign mail acceptance** task to specify recipients whose messages are accepted.
- OR -
Select the **Assign mail rejection** task to specify recipients whose messages are rejected.
4. Select the table containing the recipient from the menu at the top of the form. You have the following option:
 - Mail-enabled distribution groups
 - Dynamic distribution groups
 - Mailboxes
 - Mail users
 - Mail contacts
 - Office 365 groups
5. In the **Add assignments** pane, assign recipients.

TIP: In the **Remove assignments** pane, you can remove assigned recipients.

To remove an assignment

- Select the recipient and double-click .
6. Save the changes.

Customizing send permissions for Exchange Online dynamic distribution groups


Use the **Send on behalf of** send permission to specify which users can send messages on behalf of the distribution group.

To modify the send permission for dynamic distribution groups

1. In the Manager, select the **Azure Active Directory > Tenants > <Azure Active Directory tenant> > Exchange Online administration > Recipient configuration > Dynamic distribution groups** category.
2. Select the dynamic distribution list in the result list.
3. Select the **Assign send authorizations** task.
4. Select the table which contains the user from the menu at the top of the form. You have the following option:
 - Mail-enabled distribution groups
 - Mailboxes
 - Mail users
5. In the **Add assignments** pane, assign users.

TIP: In the **Remove assignments** pane, you can remove assigned users.

To remove an assignment

- Select the user and double-click .
6. Save the changes.

Specifying moderators for Exchange Online dynamic distribution groups

Moderated distribution groups let a moderator approve or deny messages sent to a dynamic distribution group. Only after a message has been approved by a moderator can it be forwarded to members of the dynamic distribution group.


To specify moderators for a dynamic distribution group

1. In the Manager, select the **Azure Active Directory > Dynamic distribution groups** category.
2. Select the dynamic distribution list in the result list.

3. Select the **Assign moderators** task.
4. Select the table which contains the user from the menu at the top of the form. You have the following options:
 - Mailboxes
 - Mail contacts
 - Mail users
5. In the **Add assignments** pane, add the moderators.

TIP: In the **Remove assignments** pane, you can remove assigned moderators.

To remove an assignment

- Select the moderator and double-click .
6. Save the changes.


Adding Exchange Online mail-enabled distribution groups to Exchange Online dynamic distribution groups

To add a dynamic distribution groups to mail-enabled distribution groups

1. In the Manager, select the **Azure Active Directory > Tenants > <Azure Active Directory tenant> > Exchange Online administration > Recipient configuration > Dynamic distribution groups** category.
2. Select the dynamic distribution list in the result list.
3. Select the **Assign mail-enabled distribution list** task.
4. In the **Add assignments** pane, assign mail-enabled distribution groups.

TIP: In the **Remove assignments** pane, you can remove assigned mail-enabled distribution groups.

To remove an assignment

- Select the mail-enabled distribution group and double-click .
5. Save the changes.


Related topics

- [Adding an Exchange Online dynamic distribution group to Exchange Online mail-enabled distribution groups](#) on page 144

Deleting Exchange Online dynamic distribution groups

The dynamic distribution group is permanently removed from the One Identity Manager database and Exchange Online system.

To delete a dynamic distribution group

1. In the Manager, select the **Azure Active Directory > Tenants > <Azure Active Directory tenant> > Exchange Online administration > Recipient configuration > Dynamic distribution groups** category.
2. Select the dynamic distribution list in the result list.
3. Click  in the result list.
4. Confirm the security prompt with **Yes**.

Exchange Online mail-enabled public folders

Public folders are used to allow employees shared access to information. Public folders can be structured hierarchically and are connected with a public folder database. Mail-enabling a public folder allows users to send messages to it.

Mail-enabled public folders are loaded into the One Identity Manager database by synchronization and cannot be edited in One Identity Manager.

Detailed information about this topic

- [Displaying information about Exchange Online mail-enabled public folders](#) on page 175
- [Assigning Exchange Online mail-enabled distribution groups to Exchange Online mail-enabled public folders](#) on page 176
- [Exchange Online public folders](#) on page 83
- [Synchronizing single objects](#) on page 46

Displaying information about Exchange Online mail-enabled public folders

To display information about mail-enabled public folders

1. In the Manager, select the **Azure Active Directory > Tenants > <Azure Active Directory tenant> > Exchange Online administration > Recipient configuration > Mail-enabled public folders** category.
2. Select the mail-enabled distribution group in the result list.
3. Select one of the following tasks:
 - **Exchange Online public folder overview:** This shows you an overview of the mail-enabled public folder and its dependencies.

- **Change main data:** Shows the mail-enabled public folder's main data.
- **Assign mail acceptance:** Shows which recipients can accept messages.
- **Assign mail rejection:** Shows which recipients can reject messages.
- **Assign send permissions:** Shows who can send messages on behalf of the mail enabled public folder.
- **Assign moderators:** Shows who can accept or reject messages send to a moderated mail-enabled public folder.
- **Assign mail-enabled distribution groups:** Shows which mail-enabled distribution groups are assigned. You can assign more mail-enabled distribution group or remove them.

Related topics

- [Assigning Exchange Online mail-enabled distribution groups to Exchange Online mail-enabled public folders](#) on page 176
- [Exchange Online public folders](#) on page 83
- [Synchronizing single objects](#) on page 46


Assigning Exchange Online mail-enabled distribution groups to Exchange Online mail-enabled public folders

To assign mail-enabled distribution groups to a mail-enabled public folder

1. In the Manager, select the **Azure Active Directory > Tenants > <Azure Active Directory tenant> > Exchange Online administration > Recipient configuration > Mail-enabled public folders** category.
2. Select the mail-enabled distribution group in the result list.
3. Select the **Assign mail-enabled distribution list** task.
4. In the **Add assignments** pane, assign mail-enabled distribution groups.

TIP: In the **Remove assignments** pane, you can remove assigned mail-enabled distribution groups.

To remove an assignment

- Select the mail-enabled distribution group and double-click .
5. Save the changes.

Related topics

- [Adding Exchange Online mail-enabled public folder to Exchange Online mail-enabled distribution groups](#) on page 144

Reports about Exchange Online objects

One Identity Manager makes various reports available containing information about the selected base object and its relations to other One Identity Manager database objects. The following reports are available for Exchange Online.

NOTE: Other sections may be available depending on the which modules are installed.

Table 22: Data quality target system report

Report	Published for	Description
Show overview	Mailbox Mail users Mail contact	This report shows an overview of the user account and the assigned permissions.
Show overview including origin	Mailbox Mail users Mail contact	This report shows an overview of the user account and origin of the assigned permissions.
Show overview including history	Mailbox Mail user Mail contact	This report shows an overview of the user accounts including its history. Select the end date for displaying the history (Min. date). Older changes and assignments that were removed before this date, are not shown in the report.
Overview of all assignments	Mail-enabled distribution group Office 365 group	This report finds all roles containing employees who have the selected system entitlement.

Report	Published for	Description
Show overview	Mail-enabled distribution group Office 365 group	This report shows an overview of the system entitlement and its assignments.
Show overview including origin	Mail-enabled distribution group Office 365 group	This report shows an overview of the system entitlement and origin of the assigned user accounts.
Show overview including history	Mail-enabled distribution group Office 365 group	<p>This report shows an overview of the system entitlement and including its history.</p> <p>Select the end date for displaying the history (Min. date). Older changes and assignments that were removed before this date, are not shown in the report.</p>

Configuration parameters for managing an Exchange Online environment

The following configuration parameters are additionally available in One Identity Manager after the module has been installed.

Table 23: Configuration parameters for managing an Exchange Online environment

Configuration parameters	Meaning
TargetSystem AzureAD ExchangeOnline	<p>Preprocessor relevant configuration parameter for controlling database model components for Exchange Online target system administration. If the parameter is set, the target system components are available. Changes to this parameter require the database to be recompiled.</p> <p>If you disable the configuration parameter at a later date, model components and scripts that are not longer required, are disabled. SQL procedures and triggers are still carried out. For more information about the behavior of preprocessor relevant configuration parameters and conditional compiling, see the <i>One Identity Manager Configuration Guide</i>.</p>
TargetSystem AzureAD ExchangeOnline Accounts	Allows configuration of recipient data.
TargetSystem AzureAD ExchangeOnline Accounts MailTemplateDefaultValues	Mail template used to send notifications about whether default IT operating data mapping values are used for automatically creating a user account. The Employee - new user account with default properties created mail template is used.
TargetSystem AzureAD ExchangeOnline	Default email address of the recipient for notifications about actions in the target system.

Configuration parameters	Meaning
--------------------------	---------

DefaultAddress	
----------------	--

TargetSystem AzureAD ExchangeOnline MaxFullsyncDuration	Maximum runtime of a synchronization in minutes. No recalculation of group memberships by the DBQueue Processor can take place during this time. If the maximum runtime is exceeded, group membership are recalculated.
---------------------------------------------------------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

QER ITShop AutoPublish O3EDL	Preprocessor relevant configuration parameter for automatically adding Exchange Online mail-enabled distribution groups to the IT Shop. If the parameter is set, all distribution groups are automatically assigned as products to the IT Shop. Changes to this parameter require the database to be recompiled.
------------------------------------	------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

If you disable the configuration parameter at a later date, model components and scripts that are not longer required, are disabled. SQL procedures and triggers are still carried out. For more information about the behavior of preprocessor relevant configuration parameters and conditional compiling, see the *One Identity Manager Configuration Guide*.

QER ITShop AutoPublish O3EDL ExcludeList	List of all Exchange Online mail-enabled distribution groups that must not be automatically assigned to the IT Shop. Each entry is part of a regular search pattern and supports regular expression notation.
--------------------------------------------------	---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

Example:

```
.*Administrator.*|Exchange.*|.*Admins|.*Operators|IIS_IUSRS
```

QER ITShop AutoPublish O3EUnifiedGroup	Preprocessor relevant configuration parameter for automatically adding Office 365 groups to the IT Shop. If the parameter is set, all groups are automatically assigned as products to the IT Shop. Changes to this parameter require the database to be recompiled.
----------------------------------------------	----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

If you disable the configuration parameter at a later date, model components and scripts that are not longer required, are disabled. SQL procedures and triggers are still carried out. For more information about the behavior of preprocessor relevant configuration parameters and conditional compiling, see the *One Identity Manager Configuration Guide*.

QER ITShop AutoPublish O3EUnifiedGroup ExcludeList	List of all Office 365 groups that must not be automatically assigned to the IT Shop. Each entry is part of a regular search pattern and supports regular expression notation.
------------------------------------------------------------	--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

Default project template for Exchange Online

A default project template ensures that all required information is added in One Identity Manager. This includes mappings, workflows, and the synchronization base object. If you do not use a default project template you must declare the synchronization base object in One Identity Manager yourself.

Use a default project template for initially setting up the synchronization project. For custom implementations, you can extend the synchronization project with the Synchronization Editor.

The project template uses mappings for the following schema types.

Table 24: Exchange Online schema type mapping

Schema type in Exchange Online	Table in the One Identity Manager Schema
DistributionGroup	O3EDL
DynamicDistributionGroup	O3EDynDL
Mailbox	O3EMailbox
MailContact	O3EMailContact
MailPublicFolder	O3EMailPublicFolder
MailUser	O3EMailUser
MobileDeviceMailboxPolicy	O3EMobileDeviceMBPolicy
OWAMailboxPolicy	O3EOwaMailboxPolicy
PublicFolder	O3EPublicFolder
RetentionPolicy	O3ERetentionPolicy
RoleAssignmentPolicy	O3ERoleAssignmentPolicy
SharingPolicy	O3ESharingPolicy
UnifiedGroup	O3EUnifiedGroup

Editing Exchange Online system objects

The following table describes permitted editing methods of Exchange Online schema types and names restrictions required by system object processing.

Adding and deleting user mailboxes can only be done in One Identity Manager through assignment subscriptions in Azure Active Directory. This creates a mailbox that does not appear in the database until it has been synchronized. Afterward, it can be provisioned automatically in Exchange Online.

Table 25: Methods available for editing schema types

Type	Read	Add	Delete	Refresh
Public folder (PublicFolder)	Yes	No	No	No
Mail-enabled public folder (MailPublicFolder)	Yes	No	No	No
Policy for role assignment (RoleAssignmentPolicy)	Yes	No	No	No
Mailbox policy for mobile devices (MobileDeviceMailboxPolicy)	Yes	No	No	No
Sharing policy (SharingPolicy)	Yes	No	No	No
Retention policy (RetentionPolicy)	Yes	No	No	No
Outlook Web App mailbox policy (OWAMailboxPolicy)	Yes	No	No	No
Mail user (MailUser)	Yes	Yes	Yes	Yes
Mail contact (MailContact)	Yes	Yes	Yes	Yes
Mailbox: resource mailbox (Mailbox)	Yes	Yes	Yes	Yes
Mailbox: shared mailbox (Mailbox)	Yes	Yes	Yes	Yes
Mailbox: user mailbox (Mailbox)	Yes	No	No	Yes
Mailbox: calendar settings (Mailbox)	Yes	Yes	Yes	Yes
Mailbox: statistics (Mailboxstatistics)	Yes	Yes	Yes	Yes

Type	Read	Add	Delete	Refresh
Mail-enabled distribution mailbox (DistributionGroup)	Yes	Yes	Yes	Yes
Dynamic distribution group (DynamicDistributionGroup)	Yes	No	Yes	Yes
Office 365 group (UnifiedGroup)	Yes	Yes	Yes	Yes

Exchange Online connector settings

The following settings are configured for the system connection with the Exchange Online connector.

Table 26: Exchange Online connector settings

Setting	Meaning
User name	Fully qualified name (FQDN) of the user account and password for logging in to Exchange Online. Example: <user>@<domain.com> sync.user@yourorganisation.onmicrosoft.com Variable: CP_Username
Password	The user account's password. Variable: CP_Password
Use local server time for the revision	Revision filtering data If the value is True , the local server time of the server is used for revision filtering. (default) This makes it unnecessary to load target system object for determining the revision. If the value is false , the change time stamp of the underlying Azure Active Directory objects are used for revision filtering. Variable: CP_UseLocalServerTimeAsRevision
Max. time difference (local/remote) in minutes	Revision filtering data Defines the maximum time difference in minutes between the synchronization server and the Exchange Online server. The default value is 60 minutes. If the time difference is more than 60 minutes, alter the value. Variable: CP_LocalServerRevisionMaxDifferenceInMinutes
Max. concurrent connec-	Maximum number of connections that can be used concurrently. The value must be between 1 and 20 .

Setting	Meaning
tions	Default value: 2 Variable: CP_ConnectionPoolSize
Definition of Windows PowerShell commands	You can use this setting to adjust the definition used by the connector in order to convert inputs and outputs between the Exchange Online Cmdlets and the schema of the Synchronization Engine. IMPORTANT: You should only make changes to the connector definition with the help of support desk staff. Changes to this setting will have wide ranging effects on synchronization and must be made carefully.

One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

Contacting us

For sales and other inquiries, such as licensing, support, and renewals, visit <https://www.oneidentity.com/company/contact-us.aspx>.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at <https://support.oneidentity.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to videos at www.YouTube.com/OneIdentity
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product

A

- account definition 54
 - add to IT Shop 69
 - assign automatically 67
 - assign to all employees 67
 - assign to Azure Active Directory tenant 71
 - assign to business role 66
 - assign to cost center 66
 - assign to department 66
 - assign to employee 64, 68
 - assign to location 66
 - assign to system roles 68
 - create 55
 - delete 71
 - edit 56
 - IT operating data 61-62
 - manage level 58-59
- architecture overview 10
- Azure Active Directory tenant
 - account definition mail contact (initial) 71
 - account definition mail user (initial) 71
 - account definition mailbox (initial) 71
- Azure Active Directory user account
 - assign Office 365 group 164
 - can inherit Exchange Online group 156
 - category 165

B

- base object 33, 41

C

- calculation schedule 44
 - deactivate 45
- configuration parameter 180
- convert connection parameter 33

D

- direction of synchronization
 - direction target system 23, 32
 - in the Manager 23
- dynamic distribution group 168
 - add mail-enabled distribution groups 173
 - addressing 169
 - alias 169
 - assign mail-enabled distribution group 144
 - condition 169
 - display name 169
 - edit 168
 - expansion server 169
 - identifier 169
 - limit 169
 - mail acceptance 171
 - moderator 172
 - receive restriction 171

- recipient type 169
- send on behalf of 172

E

- Exchange Online
 - advanced settings 35
- Exchange Online connector 10
- Exchange Online mailbox 86, 88
- Exchange Online organization
 - application roles 11
 - target system manager 11, 74
- Exchange Online structure 82
 - public folder 83
 - sharing policy 84

I

- IT operating data
 - change 63
- IT Shop shelf
 - assign account definition 69

J

- Job server 76
 - edit 18
 - load balancing 42

L

- load balancing 42

M

- mail-enabled distribution group 122
 - add to IT Shop 136-137
 - add to system role 135

- addressing 124
- administrator 129
- alias 124
- assign dynamic distribution group 144
- assign email user 139, 141
- assign mail-enabled distribution group 143
- assign mail-enabled public folder 144, 176
- assign mail contact 139, 142
- assign mailbox 139-140
- assign to business role 134
- assign to cost center 132
- assign to department 132
- assign to location 132
- category 142
- create 123
- delete 145, 174
- display name 124
- edit 123
- extended property 145
- join 124
- leave 124
- mail acceptance 127
- moderate 124
- moderator 128
- receive restriction 127
- send on behalf of 127
- mail-enabled public folder 175
 - assign mail-enabled distribution group 144, 176
- mail contact 112
 - account definition 71, 114
 - addressing 114
 - alias 114

- assign mail-enabled distribution group 139, 142
- category 142
- create 113
- delete 121
- destination address 114
- display name 114
- employee 114
- extended property 120
- mail acceptance 118
- manage level 114
- moderator 120
- receive restriction 118
- restore 121
- send on behalf of 119
- mail user 102
 - account definition 71, 104
 - Active Directory user account 104
 - addressing 104
 - alias 104
 - assign mail-enabled distribution group 139, 141
 - category 142
 - create 103
 - delete 111
 - destination address 104
 - display name 104
 - edit 103
 - employee 104
 - extended property 111
 - mail acceptance 109
 - manage level 104
 - moderator 110
 - receive restriction 109
 - restore 111
 - send on behalf of 109
- mailbox
 - addressing 89
 - alias 89
 - alternative recipient 89
 - archive size 92
 - assign mail-enabled distribution group 139-140
 - Azure Active Directory user account 89
 - book 95
 - Calendar Attendant 95
 - calendar setting 95
 - category 142
 - connected mailbox 89
 - create 87
 - deactivate 89
 - delete 101
 - discovery mailbox 86
 - display name 89
 - edit 88
 - employee 89
 - equipment mailbox 86, 95
 - extended property 100
 - folder policy 89
 - functions 92
 - limit 91
 - linked mailbox 86
 - mail acceptance 98
 - mailbox database 89
 - mailbox type 86, 89
 - mailbox usage 91
 - meeting request 97
 - moderator 100
 - Outlook Web App mailbox policy 89
 - personal archive 92
 - policies 92

- receive restriction 98
- Resource Attendant 95
- resource mailbox 86, 95
- restore 101
- role assignment policy 89
- room mailbox 86, 95
- send on behalf of 99
- shared mailbox 86
- sharing policy 84, 89
- size 91
- user mailbox 86
- membership
 - modify provisioning 40

O

object

- delete immediately 47
- outstanding 47
- publish 47

Office 365 group 147

- Active Directory group 124, 148
- add to IT Shop 160, 162
- add to system role 159
- alias 148
- allow subscription 148, 154
- assign Azure Active Directory user account 154
- assign owner 153
- assign subscription 154
- assign to business role 158
- assign to cost center 157
- assign to department 157
- assign to location 157
- assign user account 164
- category 165

- create 147
- delete 167
- display name 148
- edit 148
- extended property 166
- mail acceptance 152
- receive restriction 152
- outstanding object 47

P

- project template 182
- provisioning
 - accelerate 42
 - members list 40
- public folder 83

R

- revision filter 38

S

- schema
 - changes 37
 - shrink 37
 - update 37
- server 76
- single object synchronization 41, 46
 - accelerate 42
- start up configuration 33
- synchronization
 - accelerate 38
 - calculation schedule 44
 - configure 23, 31
 - connection parameter 23, 31
 - Exchange Online 14-15

- prevent 45
- scope 31
- set up 14-15
- start 23, 44
- synchronization project
 - create 23
- variable 31
- workflow 23, 32
- synchronization configuration
 - customize 31-32
- synchronization log 45
 - contents 30
 - create 30
- synchronization project
 - create 23
 - deactivate 45
 - project template 182
- synchronization server 10, 76
 - configure 18
 - install 18
 - Job server 18
- synchronization workflow
 - create 23, 32
- synchronize single object 46
- system connection
 - change 32
 - enabled variable set 34

T

- target system manager 74
- target system synchronization 47
- template
 - IT operating data, modify 63

U

- user account
 - apply template 63

V

- variable set 33
 - active 34