



syslog-ng Store Box 7.4.0

Deploying on Amazon Web Services

Copyright 2024 One Identity LLC.

ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of One Identity LLC .

The information in this document is provided in connection with One Identity products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of One Identity LLC products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, ONE IDENTITY ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ONE IDENTITY BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ONE IDENTITY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. One Identity makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. One Identity does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

One Identity LLC.
Attn: LEGAL Dept
4 Polaris Way
Aliso Viejo, CA 92656

Refer to our website (<http://www.OneIdentity.com>) for regional and international office information.

Patents

One Identity is proud of our advanced technology. Patents and pending patents may apply to this product. For the most current information about applicable patents for this product, please visit our website at <http://www.OneIdentity.com/legal/patents.aspx>.

Trademarks

One Identity and the One Identity logo are trademarks and registered trademarks of One Identity LLC. in the U.S.A. and other countries. For a complete list of One Identity trademarks, please visit our website at www.OneIdentity.com/legal/trademark-information.aspx. All other trademarks are the property of their respective owners.

Legend

 **WARNING:** A WARNING icon highlights a potential risk of bodily injury or property damage, for which industry-standard safety precautions are advised. This icon is often associated with electrical hazards related to hardware.

 **CAUTION:** A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.

SSB Deploying on Amazon Web Services
Updated - 16 April 2024, 16:37

For the most recent documents and product information, see [Online product documentation](#).

Contents

Introduction	4
Prerequisites	5
Limitations	6
Finding or copying SSB AMIs on Amazon Web Services	7
Installing SSB on Amazon Web Services	10
About us	23
Contacting us	23
Technical support resources	23

Introduction

The aim of this guide is to provide detailed, step-by-step instructions on how to set up and install syslog-ng Store Box in an Amazon Web Services (AWS) virtual environment.

NOTE: When setting up a virtual environment, carefully consider the configuration aspects such as CPU, memory availability, I/O subsystem, and network infrastructure to ensure the virtual layer has the necessary resources available. Please consult [One Identity's Product Support Policies](#) for more information on environment virtualization.

The document comprises the following sections:

- [Prerequisites](#) on page 5 collects the requirements that you must comply with before deploying SSB on AWS.
- [Limitations](#) on page 6 lists the limitations that apply when installing SSB in an AWS virtual environment.
- [Installing SSB on Amazon Web Services](#) on page 10 describes how to install SSB in an AWS virtual environment.

Prerequisites

The following prerequisites must be met before deploying SSB on Amazon Web Services:

- You have a valid One Identity syslog-ng Store Box license.
syslog-ng Store Box uses the "Bring your own license" model. Note that to deploy two active SSB nodes as an availability set, you must purchase two standalone SSB licenses. To purchase a license, [contact our Sales Team](#).
- You have an Amazon Web Services account and privileges to access the Amazon Elastic Compute Cloud (EC2) service.
- You have secure access to your Amazon Virtual Private Cloud (VPC) resources, for example, through the use of a Virtual Private Network (VPN).
- You have working knowledge of the SSB installation process.
- You have familiarity with AWS EC2.

Limitations

The following limitations apply when deploying SSB on Amazon Web Services:

- If High Availability (HA) operation mode is required in a virtual environment, use the HA function provided by the virtual environment.
- Hardware-related alerts and status indicators of SSB may display inaccurate information, for example, display degraded RAID status.
- When running SSB in a virtual environment, it is sufficient to use a single network interface.
- During AWS installation, connecting directly to the Internet using a public IP address is not supported. Instead, you must access the Internet via a Virtual Private Network or a jump host.

Finding or copying SSB AMIs on Amazon Web Services


This section describes how you can find or copy syslog-ng Store Box (SSB) [Amazon Machine Images \(AMIs\)](#) on [Amazon Web Services \(AWS\)](#).

For more information about AWS and installing SSB on AWS, see [Installing SSB on Amazon Web Services](#).

Finding or copying SSB AMIs on AWS

By default, the publicly available SSB AMIs can be found under **Services > AWS Management Console > AWS services > EC2**, in the **US West (Oregon)** region.

Figure 1: Services > AWS Management Console > AWS services > EC2 - Publicly available AMIs under the US West (Oregon) region




If you need a region other than the standard US West (Oregon), you have to copy the AMIs to the destination region of your choice.

To copy your SSB AMIs on AWS to the destination region of your choice

1. Enter your AWS Services account, and navigate to **Services > AWS Management Console > AWS services > EC2**.
2. Navigate to **Images > AMIs**, then filter the available AMIs for SSB 6 versions.


TIP: The `ssb 6` search expression will filter for the AMIs of all available release versions of SSB within the 6 release set. For more information about release version numbering in SSB, see the description of LTS and Feature releases under the [syslog-ng Store Box Product Life Cycle table](#).

Figure 2: Images > AMIs - Available AMIs after filtering for SSB 6 versions



3. Select the SSB AMI of your choice (for example, **SSB 6.0.1**), then select **Actions > Copy**, and select the **Destination region** of your choice (for example, **Asia Pacific (Tokyo)**, in this example).

Figure 3: Images > AMIs > Actions > Copy AMI pop-up window opened from <the AMI of your choice> - Customizing your AMI copying preferences



4. (Optional) Enter a **Description** for the AMI you want to copy, and enable **Encryption** if you prefer to use it.

TIP: If you are not sure what enabling **Encryption** results in, click ⓘ (info) next to **Encrypt target EBS snapshots**.

5. Click **Copy AMI** to finish copying the AMI of your choice with the settings you customize.

Installing SSB on Amazon Web Services

This section describes how to deploy syslog-ng Store Box (SSB) on Amazon Web Services (AWS).

NOTE: This section uses a number of screenshots for illustration purposes. Note that these are added here for reference only as the look and feel (but not the contents) of the Amazon user interface may change without this guide containing the most recent changes.


To deploy syslog-ng Store Box on AWS

1. Log in to [Amazon Web Services](#).
2. Once logged in, go to **INSTANCES** > **Instances** in the left-hand navigation pane, then click **Launch Instance**.

NOTE: If you can not find the SSB AMIs you are looking for listed under **Community AMIs**, you have to copy them first from the publicly available AMIs (located under **Services** > **AWS Management Console** > **AWS services** > **EC2**, in the **US West (Oregon)** region by default). For more information about copying SSB AMIs to the region of your choice, see [Finding or copying SSB AMIs on Amazon Web Services](#).

The **Step 1: Choose an Amazon Machine Image (AMI)** page appears.

Figure 4: Step 1: Choose an Amazon Machine Image (AMI)



3. Choose an [Amazon Machine Image \(AMI\)](#) that corresponds to the type of Virtual Machine (VM) that you want to launch an instance from.

To choose the AMI that corresponds to the type of Virtual Machine (VM) that you want to launch an instance from

1. Navigate to **Community AMIs**.
2. Filter the available AMIs for SSB 6.

TIP: The SSB 6\.. search expression will filter for the AMIs of all available release versions of SSB within the 6 release set. For more information about release version numbering in SSB, see the description of LTS and Feature releases under [the syslog-ng Store Box Product Life Cycle table](#).

3. Click on the SSB AMI of your choice (for example, SSB 6.0.1), and click the corresponding **Select** button.

The **Step 2: Choose an Instance Type** page comes up.

Figure 5: Step 2: Choose an Instance Type

Step 2: Choose an Instance Type

Amazon EC2 provides a wide selection of instance types optimized to fit different use cases. Instances are virtual servers that can run applications. They have varying combinations of CPU, memory, storage, and networking capacity, and give you the flexibility to choose the appropriate mix of resources for your applications. [Learn more](#) about instance types and how they can meet your computing needs.

Filter by: **All instance types** **Current generation** [Show/Hide Columns](#)

Currently selected: t2.small (Variable ECUs, 1 vCPUs, 2.5 GHz, Intel Xeon Family, 2 GiB memory, EBS only)

	Family	Type	vCPUs	Memory (GiB)	Instance Storage (GB)	EBS-Optimized Available	Network Performance
<input type="checkbox"/>	General purpose	t2.nano	1	0.5	EBS only	-	Low to Moderate
<input type="checkbox"/>	General purpose	t2.micro <small>Free tier eligible</small>	1	1	EBS only	-	Low to Moderate
<input checked="" type="checkbox"/>	General purpose	t2.small	1	2	EBS only	-	Low to Moderate
<input type="checkbox"/>	General purpose	t2.medium	2	4	EBS only	-	Low to Moderate
<input type="checkbox"/>	General purpose	t2.large	2	8	EBS only	-	Low to Moderate

[Cancel](#) [Previous](#) [Review and Launch](#) [Next: Configure Instance Details](#)

[Feedback](#) [English](#) © 2008 - 2016, Amazon Web Services, Inc. or its affiliates. All rights reserved. [Privacy Policy](#) [Terms of Use](#)

4. Choose an instance type:

- a. Select an instance type by clicking the checkbox next to it.

The minimum memory requirement is 2 GiB, that is, type **t2.small**. This instance type is able to handle 10,000 Events per Second (EPS).

The recommended memory requirement is 7.5 GB, that is, type **c4.xlarge**. The capacity of this instance type is the closest to the physical hardware.

- b. Click **Next: Configure Instance Details**.

The **Step 3: Configure Instance Details** page comes up.

Figure 6: Step 3: Configure Instance Details

Step 3: Configure Instance Details
Configure the instance to suit your requirements. You can launch multiple instances from the same AMI, request Spot instances to take advantage of the lower pricing, assign an access management role to the instance, and more.

Number of instances ⓘ 1 [Launch into Auto Scaling Group](#) ⓘ

Purchasing option ⓘ ☐ Request Spot instances

Network ⓘ vpc-49054e2c (default) [Create new VPC](#)

Subnet ⓘ subnet-2a811073 | Default in us-west-2c [Create new subnet](#)
4079 IP Addresses available

Auto-assign Public IP ⓘ Disable

IAM role ⓘ None [Create new IAM role](#)

Shutdown behavior ⓘ Stop

Enable termination protection ⓘ ☐ Protect against accidental termination

Monitoring ⓘ ☐ Enable CloudWatch detailed monitoring
[Additional charges apply.](#)

Tenancy ⓘ Shared - Run a shared hardware instance
[Additional charges will apply for dedicated tenancy.](#)

▼ **Network interfaces** ⓘ

Device	Network Interface	Subnet	Primary IP	Secondary IP addresses
eth0	New network interfa ▼	subnet-2a8110 ▼	Auto-assign	Add IP

[Cancel](#) [Previous](#) [Review and Launch](#) [Next: Add Storage](#)

[Feedback](#) [English](#) © 2008 - 2016, Amazon Web Services, Inc. or its affiliates. All rights reserved. [Privacy Policy](#) [Terms of Use](#)

5. Configure instance details:

- Select the required Virtual Private Cloud (VPC) from the **Network** list.
- Choose a subnet to launch the instance into.

NOTE: Exposing SSB to the public Internet during installation is not supported at all, therefore you must use a VPN or jump host to reach your instance and configure it.

As for exposing the logging interface to the Internet after installation, [contact our Support Team](#) to discuss your needs and how those could be met.

- Ensure that the **Auto-assign Public IP** field is set to **Disable** or **Use subnet setting (Disable)**. This is required so that you do not get assigned a public IP address.
- Use the default values for all other fields or change them as required.
- You can leave the **Network interfaces** part untouched as using just one network interface will suffice.

NOTE: If you launch SSB with a single interface configured, that interface will act as the management interface.

- f. Click **Next: Add Storage**.

The **Step 4: Add Storage** page appears.

Figure 7: Step 4: Add Storage

Services Resource Groups

1. Choose AMI 2. Choose Instance Type 3. Configure Instance 4. Add Storage 5. Tag Instance 6. Configure Security Group 7. Review

Step 4: Add Storage

Your instance will be launched with the following storage device settings. You can attach additional EBS volumes and instance store volumes to your instance, or edit the settings of the root volume. You can also attach additional EBS volumes after launching an instance, but not instance store volumes. [Learn more](#) about storage options in Amazon EC2.

Volume Type	Device	Snapshot	Size (GiB)	Volume Type	IOPS	Throughput (MB/s)	Delete on Termination	Encrypted
Root	/dev/sda1	snap-ebe05bcc	64	Provisioned IOPS	3200	N/A	<input type="checkbox"/>	Not Encrypted

[Add New Volume](#)

Free tier eligible customers can get up to 30 GB of EBS General Purpose (SSD) or Magnetic storage. [Learn more](#) about free usage tier eligibility and usage restrictions.

[Cancel](#) [Previous](#) [Review and Launch](#) [Next: Tag Instance](#)

Feedback English © 2008 - 2016, Amazon Web Services, Inc. or its affiliates. All rights reserved. Privacy Policy Terms of Use

6. Add storage to your instance:

- a. Set the size of your instance's store volume.

NOTE: It is important that you choose this value wisely as once you have launched the instance, you will not be able to go back and modify it. The minimum storage size is 8 GB, while the maximum allowed value is 16 TB (16384 GB).

- b. Set the volume type of your instance's store volume.

TIP: Consider the following recommendations:

- SSD provides better performance than an HDD, but it is also more expensive.
- If you choose a volume larger than 500 GB, or your SSB is expected to handle volumes of traffic lower than 15,000 EPS, then select volume type **General Purpose SSD (GP2)**. This volume type comes with an I/O credit balance that is used when your volume requires more I/O operations per second (IOPS) than the baseline performance I/O level. If you empty your credit balance, the maximum IOPS performance of the volume will remain at the baseline IOPS performance level, which may result in suboptimal performance.

- If your SSB is required to handle traffic exceeding 15,000 EPS or you choose a volume that is smaller than 500 GB in size, then select volume type **Provisioned IOPS SSD (IO1)**. This volume type does not use a credit model: instead, it allows you to specify a consistent IOPS rate.
- Selecting the **Delete on Termination** checkbox will automatically delete your store volume on terminating the instance. This is useful as this will free up storage place, and you will not have to pay for a store volume you are not using anymore. However, deleting the store volume will also delete your logs.

c. Click **Next: Tag Instance**.

The **Step 5: Tag Instance** page comes up.

Figure 8: Step 5: Tag Instance

Step 5: Tag Instance

A tag consists of a case-sensitive key-value pair. For example, you could define a tag with key = Name and value = Webserver. [Learn more](#) about tagging your Amazon EC2 resources.

Key (127 characters maximum)	Value (255 characters maximum)
Name	demo
Product	SSB

Create Tag (Up to 50 tags maximum)

Cancel Previous **Review and Launch** Next: Configure Security Group

7. Create a tag for your instance:

- Add a meaningful key-value pair that will help you later on to easily identify your instance.
- Click **Next: Configure Security Group**.

The **Step 6: Configure Security Group** page appears.

Figure 9: Step 6: Configure Security Group

Step 6: Configure Security Group

A security group is a set of firewall rules that control the traffic for your instance. On this page, you can add rules to allow specific traffic to reach your instance. For example, if you want to set up a web server and allow Internet traffic to reach your instance, add rules that allow unrestricted access to the HTTP and HTTPS ports. You can create a new security group or select from an existing one below. [Learn more](#) about Amazon EC2 security groups.

Assign a security group: ☐ Create a new security group ☒ Select an existing security group

Security Group ID	Name	Description	Actions
sg-067e2a60	allowinternal	Allow traffic inside the vpc	Copy to new

Inbound rules for sg-067e2a60 (Selected security groups: sg-067e2a60)

Type	Protocol	Port Range	Source
All traffic	All	All	172.31.0.0/16

[Cancel](#) [Previous](#) [Review and Launch](#)

8. Configure security group:

- a. Set a new or an existing security group to control how SSB is accessed.

Exposing SSB to the public Internet during installation is not supported at all, therefore you must use a VPN or jump host to reach your instance and configure it. As for exposing the logging interface to the Internet after installation, contact Support to discuss your needs and how those could be met.

To achieve the above: restrict your security group to those users and log clients that access SSB from a secure network, and not over the public Internet. For example, if you are using a jump host, then you need a security group that will allow only your dedicated VPC to connect to your SSB. If there is a VPN to your home network or some other secure network, that can be allowed as well.

- b. Click **Review and Launch**.

The **Step 7: Review Instance Launch** page comes up.

Figure 10: Step 7: Review Instance Launch

Step 7: Review Instance Launch
Please review your instance launch details. You can go back to edit changes for each section. Click **Launch** to assign a key pair to your instance and complete the launch process.

Warning: Your instance configuration is not eligible for the free usage tier. To launch an instance that's eligible for the free usage tier, check your AMI selection, instance type, configuration options, or storage devices. Learn more about [free usage tier](#) eligibility and usage restrictions.

[Don't show me this again](#)

AMI Details [Edit AMI](#)

import-ami-fh6rahaf - ami-8173d1e1
AWS-VMImport service: Linux - Ubuntu 12.04.5 LTS 'ln vl - 3.13.0-32-generic
Root Device Type: ebs Virtualization type: hvm

Instance Type [Edit instance type](#)

Instance Type	ECUs	vCPUs	Memory (GiB)	Instance Storage (GB)	EBS-Optimized Available	Network Performance
t2.small	Variable	1	2	EBS only	-	Low to Moderate

Security Groups [Edit security groups](#)

Security Group ID	Name	Description
sg-067e2a60	allowinternal	Allow traffic inside the vpc

All selected security groups inbound rules


Security Group ID	Type	Protocol	Port Range	Source
sg-067e2a60	All traffic	All	All	172.31.0.0/16

[Cancel](#) [Previous](#) [Launch](#)

9. Before launching your instance, double-check whether all details have been set as intended:
 - a. Ensure that:
 - Under **Instance Type**, you have at least 2 GB of memory assigned.
 - Under **Instance Details**, the **Assign Public IP** option is set to **Disable** or **Use subnet setting (Disable)**.
 - b. Make any changes if required.
 - c. Once you are happy with all settings, click **Launch**.

The **Select an existing key pair or create a new key pair** pop-up window comes up.

Figure 11: Step 7: Review Instance Launch — Key pair pop-up window



10. On the **Select an existing key pair or create a new key pair** pop-up window:
 - a. Select the **Proceed without a key pair** option.
 - b. Select **I acknowledge that I will not be able to connect to this instance unless I already know the password built into this AMI.**
 - c. Click **Launch Instances.**

The **Launch Status** page comes up informing you that your instance is launching.

Figure 12: Launch Status page

Launch Status

✓ **Your instances are now launching**
The following instance launches have been initiated: [i-785f9fd6](#) [View launch log](#)

i **Get notified of estimated charges**
[Create billing alerts](#) to get an email notification when estimated charges on your AWS bill exceed an amount you define (for example, if you exceed the free usage tier).

How to connect to your instances

Your instances are launching, and it may take a few minutes until they are in the **running** state, when they will be ready for you to use. Usage hours on your new instances will start immediately and continue to accrue until you stop or terminate your instances.

Click **View Instances** to monitor your instances' status. Once your instances are in the **running** state, you can **connect** to them from the Instances screen. [Find out](#) how to connect to your instances.

▼ Here are some helpful resources to get you started

- [How to connect to your Linux instance](#)
- [Amazon EC2: User Guide](#)
- [Learn about AWS Free Usage Tier](#)
- [Amazon EC2: Discussion Forum](#)

While your instances are launching you can also

- [Create status check alarms](#) to be notified when these instances fail status checks. (Additional charges may apply)
- [Create and attach additional EBS volumes](#) (Additional charges may apply)
- [Manage security groups](#)

[View Instances](#)

Feedback English © 2008 - 2016, Amazon Web Services, Inc. or its affiliates. All rights reserved. Privacy Policy Terms of Use


11. To view your instance's status, click **View Instances**.

The **Instances** page comes up, which should now display the instance you have just launched. Depending on the size of the instance, installation may take up to 1-5 minutes.

To access your SSB instance and start configuring it using the welcome wizard, you will need your instance's IP address and the netmask of your chosen subnet, both of which you can obtain from the AWS user interface.


12. SSB expects that the IP address provided will not change. Therefore, before retrieving the IP address, perform the following check:
 - a. Click the instance you have just added, and select **Actions > Networking > Manage Private IP Addresses** from the menu at the top.

Figure 13: Instances page — Actions menu



The **Manage Private IP Addresses** pop-up window comes up.

Figure 14: Instances page — Manage Private IP Addresses pop-up window



- b. To ensure that the IP address stays the same, make sure that the **Allow reassignment** option is unchecked.

Note down the netmask of the subnet you selected (**/20** in the example provided) because you will need this piece of information later on, when configuring SSB via the welcome wizard.

13. To obtain and use the IP address of the instance:

- a. Click the instance on the **Instances** page.

This will display the description of the instance, including its private IP address.

Figure 15: Instances page — instance description

The screenshot shows the AWS Management Console 'Instances' page. The left sidebar contains navigation links for EC2 Dashboard, Events, Tags, Reports, Limits, INSTANCES, Spot Requests, Reserved Instances, Scheduled Instances, Dedicated Hosts, IMAGES, AMIs, Bundle Tasks, ELASTIC BLOCK STORE, Volumes, Snapshots, NETWORK & SECURITY, Security Groups, Elastic IPs, Placement Groups, Key Pairs, Network Interfaces, LOAD BALANCING, Load Balancers, Target Groups, AUTO SCALING, Launch Configurations, Auto Scaling Groups, COMMANDS, Command History, and Documents. The main content area shows a list of instances with columns: Name, Instance ID, Instance Type, Instance State, Public DNS, Public IP, and Security Groups. The 'demo' instance (ID: i-785f9fd6) is selected. Below the list, the 'Instance: i-785f9fd6 (demo)' details are shown, including Private IP: 172.31.5.17. The 'Description' tab is active, displaying various instance attributes in a key-value format. The 'Private IP' value '172.31.5.17' is highlighted with a red box.

Name	Instance ID	Instance Type	Instance State	Public DNS	Public IP	Security Groups
AWS tech-preview	i-eb768137	t2.small	running	-	-	allowinternal
ssb-proxy	i-47a6652b	t1.micro	running	-	-	ssbtest, allowinte...
demo	i-785f9fd6	t2.small	running	-	-	allowinternal

Instance: **i-785f9fd6 (demo)** Private IP: 172.31.5.17

Attribute	Value
Instance ID	i-785f9fd6
Instance state	running
Instance type	t2.small
Private DNS	ip-172-31-5-17.us-west-2.compute.internal
Private IPs	172.31.5.17
Secondary private IPs	-
VPC ID	vpc-49054e2c
Subnet ID	subnet-2a811073
Network interfaces	eth0
Source/dest. check	True
EBS-optimized	False
Root device type	ebs
Root device	/dev/sda1
Block devices	/dev/sda1
Public DNS	-
Public IP	-
Elastic IPs	-
Availability zone	us-west-2c
Security groups	allowinternal, view rules
Scheduled events	No scheduled events
AMI ID	import-ami-fb6rahaaf (ami-8173d1e1)
Platform	-
IAM role	-
Key pair name	-
Owner	128059300227
Launch time	November 15, 2016 at 9:51:17 AM UTC+1 (less than one hour)
Termination protection	False
Lifecycle	normal
Monitoring	basic

- Select the value in the **Private IPs** field and copy it.
- Paste this value in the **Networking > External interface > IP address** field of the SSB welcome wizard.

For detailed information on the SSB welcome wizard, see *The Welcome Wizard and the first login* in the *Administration Guide*.

14. To obtain and use the subnet's netmask:

- Retrieve the netmask information you noted down earlier in Step 12b.
- AWS provides the netmask value in CIDR format (for example, /24), while SSB expects this value in the octet format (for example, 255.255.255.0).

Convert the value from the CIDR to the octet format.

- Enter the result in the **Networking > External interface > Netmask** field of the SSB welcome wizard.

For detailed information on the SSB welcome wizard, see *The Welcome Wizard and the first login* in the *Administration Guide*.

One Identity solutions eliminate the complexities and time-consuming processes often required to govern identities, manage privileged accounts and control access. Our solutions enhance business agility while addressing your IAM challenges with on-premises, cloud and hybrid environments.

Contacting us

For sales and other inquiries, such as licensing, support, and renewals, visit <https://www.oneidentity.com/company/contact-us.aspx>.

Technical support resources

Technical support is available to One Identity customers with a valid maintenance contract and customers who have trial versions. You can access the Support Portal at <https://support.oneidentity.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. The Support Portal enables you to:

- Submit and manage a Service Request
- View Knowledge Base articles
- Sign up for product notifications
- Download software and technical documentation
- View how-to videos at www.YouTube.com/OneIdentity
- Engage in community discussions
- Chat with support engineers online
- View services to assist you with your product